


Lab 12 Configuración ASA desde la CLI



Configuraciones ASA

- **ciscoasa(config)#hostname CCNAS-ASA**
- **CCNAS-ASA(config)#domain-name ccnasecurity.com**
- **CCNAS-ASA(config)#enable password ciscoenpa55**

Configuraciones ASA


- CCNAS-ASA(config)# interface vlan 1
- CCNAS-ASA(config-if)# nameif inside
- CCNAS-ASA(config-if)# ip address 192.168.1.1 255.255.255.0
- CCNAS-ASA(config-if)# security-level **100**

Configuraciones ASA

- CCNAS-ASA(config-if)# interface vlan 2
- CCNAS-ASA(config-if)# nameif outside
- CCNAS-ASA(config-if)# ip address 209.165.200.226 255.255.255.248
- CCNAS-ASA(config-if)# security-level 0

Ruta por defecto en ASA

- CCNAS-ASA(config)# route outside 0.0.0.0 0.0.0.0 209.165.200.225



PAT en ASA

- CCNAS-ASA(config)# object network **inside-net**
- CCNAS-ASA(config-network-object)# subnet 192.168.1.0 255.255.255.0
- CCNAS-ASA(config-network-object)# nat (inside,outside) dynamic interface
- CCNAS-ASA(config-network-object)# end

Política de inspección en ASA

- CCNAS-ASA(config)# class-map **inspection_default**
- CCNAS-ASA(config-cmap)# match default-inspection-traffic
- CCNAS-ASA(config-cmap)# exit
- CCNAS-ASA(config)# policy-map **global_policy**
- CCNAS-ASA(config-pmap)# class **inspection_default**
- CCNAS-ASA(config-pmap-c)# inspect icmp
- CCNAS-ASA(config-pmap-c)# exit
- CCNAS-ASA(config)# service-policy **global_policy** global

DHCP en ASA

- **CCNAS-ASA(config)# dhcpd address 192.168.1.5-192.168.1.36 inside**
- **CCNAS-ASA(config)# dhcpd dns 209.165.201.2 interface inside**
- **CCNAS-ASA(config)# dhcpd enable inside**

AAA en ASA

- CCNAS-ASA(config)# username **admin** password **adminpa55**
- CCNAS-ASA(config)# aaa authentication ssh console LOCAL
- CCNAS-ASA(config)# crypto key generate rsa modulus 1024
- CCNAS-ASA(config)# ssh 192.168.1.0 255.255.255.0 inside
- CCNAS-ASA(config)# ssh 172.16.3.3 255.255.255.255 outside
- CCNAS-ASA(config)# ssh timeout 10

Conectividad SSH

- **PCC> ssh -l admin 209.165.200.226**
- **PCB> ssh -l admin 192.168.1.1**

DMZ en ASA

- CCNAS-ASA(config)# interface vlan 3
- CCNAS-ASA(config-if)# ip address 192.168.2.1 255.255.255.0
- CCNAS-ASA(config-if)# no forward interface vlan 1
- CCNAS-ASA(config-if)# nameif dmz
- CCNAS-ASA(config-if)# security-level **70**
- CCNAS-ASA(config-if)# interface Ethernet0/2
- CCNAS-ASA(config-if)# switchport access vlan 3

NAT estático en ASA

- CCNAS-ASA(config)# object network **dmz-server**
- CCNAS-ASA(config-network-object)# host 192.168.2.3
- CCNAS-ASA(config-network-object)# nat (dmz,outside) static 209.165.200.227
- CCNAS-ASA(config-network-object)# exit

ACL que permita tráfico desde INTERNET hacia la DMZ

- CCNAS-ASA(config)# access-list OUTSIDE-DMZ permit icmp any host 192.168.2.3
- CCNAS-ASA(config)# access-list OUTSIDE-DMZ permit tcp any host 192.168.2.3 eq 80
- CCNAS-ASA(config)# access-group OUTSIDE-DMZ in interface outside